

PERFORCE

# **C/C++ API User Guide**

2016.2

*October 2016*

---

## **C/C++ API User Guide**

### **2016.2**

October 2016

Copyright © 1999-2016 Perforce Software.

All rights reserved.

Perforce software and documentation is available from <http://www.perforce.com/>. You can download and use Perforce programs, but you can not sell or redistribute them. You can download, print, copy, edit, and redistribute the documentation, but you can not sell it, or sell any documentation derived from it. You can not modify or attempt to reverse engineer the programs.

This product is subject to U.S. export control laws and regulations including, but not limited to, the U.S. Export Administration Regulations, the International Traffic in Arms Regulation requirements, and all applicable end-use, end-user and destination restrictions. Licensee shall not permit, directly or indirectly, use of any Perforce technology in or by any U.S. embargoed country or otherwise in violation of any U.S. export control laws and regulations.

Perforce programs and documents are available from our Web site as is. No warranty or support is provided. Warranties and support, along with higher capacity servers, are sold by Perforce Software.

Perforce Software assumes no responsibility or liability for any errors or inaccuracies that might appear in this book. By downloading and using our programs and documents you agree to these terms.

Perforce and Inter-File Branching are trademarks of Perforce Software.

All other brands or product names are trademarks or registered trademarks of their respective companies or organizations.

Any additional software included within Perforce software is listed in [License Statements on page 307](#).

---

# Table of Contents

About This Manual .....	xxi
Helix documentation .....	xxi
Syntax conventions .....	xxii
Please give us feedback .....	xxii
<b>Chapter 1 Overview .....</b>	<b>1</b>
Release compatibility of the API .....	1
Purpose of the API .....	1
Architecture of the API .....	1
API files .....	1
<b>Chapter 2 Application Programming .....</b>	<b>3</b>
Compiling and linking Perforce applications .....	3
Link order .....	3
SSL support .....	3
OpenSSL Library Version .....	3
Link order for SSL support .....	4
Compiler support .....	4
UNIX .....	4
Linux .....	4
Windows .....	4
Sample Jamfile .....	5
Sample Makefile .....	5
Building with Jam .....	5
Building the sample application .....	6
Sending commands to the versioning service .....	8
Perforce settings on the user's machine .....	9
Connecting to the server .....	9
Displaying Perforce forms .....	9
Sending commands .....	10
Processing data from the server .....	10
Tagged data .....	10
Untagged Data .....	12
Disconnecting from the server .....	12
Performing file I/O .....	12
Handling errors .....	15
Connection errors .....	16
Server errors .....	16
Class overviews .....	16
ClientApi - Perforce server connections and commands .....	16
ClientProgress - progress indicators for Perforce commands .....	17

ClientUser - I/O for Perforce commands .....	17
Error - collect and report layered errors .....	17
ErrorLog - output error messages .....	18
FileSys - Perforce file I/O .....	18
Ignore - support for rejecting files .....	18
KeepAlive - support for client-side disconnection .....	18
MapApi - logic for view mappings .....	19
Options - parse and store command line options .....	19
ServerHelperApi - helper methods for creating personal servers .....	19
Signaler - interrupt handling .....	19
StrBuf - string manipulation .....	19
StrDict - field/value manipulation .....	20
StrNum - small numeric strings .....	20
StrOps - string operations .....	20
StrPtr - text operations .....	20
StringRef - refer to existing strings .....	20
<b>Chapter 3    Public Methods Reference .....</b>	<b>21</b>
ClientApi methods .....	21
ClientApi::DefineClient( const char *, Error * ) .....	21
Notes .....	21
Example .....	21
ClientApi::DefineHost( const char *, Error * ) .....	22
Notes .....	22
Example .....	22
ClientApi::DefineIgnoreFile( const char *, Error * ) .....	23
Notes .....	23
See also .....	23
Example .....	23
ClientApi::DefinePassword( const char *, Error * ) .....	24
Notes .....	24
Example .....	24
ClientApi::DefinePort( const char *, Error * ) .....	25
Notes .....	25
Example .....	25
ClientApi::DefineUser( const char *, Error * ) .....	26
Notes .....	26
Example .....	26
ClientApi::Dropped() .....	27
Notes .....	27
Example .....	27
ClientApi::Final( Error * ) .....	28
Notes .....	28
Example .....	28
ClientApi::GetClient() .....	29
Notes .....	29
Example .....	29
ClientApi::GetConfig() .....	30

Notes .....	30
Example .....	30
ClientApi::GetCwd() .....	31
Notes .....	31
Example .....	31
ClientApi::GetHost() .....	32
Notes .....	32
Example .....	32
ClientApi::GetIgnore() .....	33
Notes .....	33
See also .....	33
Example .....	33
ClientApi::GetIgnoreFile() .....	34
Notes .....	34
See also .....	34
Example .....	34
ClientApi::GetOs() .....	35
Notes .....	35
Example .....	35
ClientApi::GetPassword() .....	36
Notes .....	36
Example .....	36
ClientApi::GetPort() .....	37
Notes .....	37
Example .....	37
ClientApi::GetProtocol( const char * ) .....	38
Notes .....	38
Example .....	38
ClientApi::GetUser() .....	39
Notes .....	39
Example .....	39
ClientApi::Init( Error * ) .....	40
Notes .....	40
Example .....	40
ClientApi::Run( const char *, ClientUser * ) .....	41
Notes .....	41
Example .....	41
ClientApi::SetBreak( KeepAlive *breakCallback ) .....	42
Notes .....	42
See also .....	42
Example .....	42
ClientApi::SetClient( const StrPtr * ) .....	44
Notes .....	44
Example .....	44
ClientApi::SetClient( const char * ) .....	45
Notes .....	45
Example .....	45
ClientApi::SetCwd( const StrPtr * ) .....	46
Notes .....	46
Example .....	46
ClientApi::SetCwd( const char * ) .....	47

Notes .....	47
Example .....	47
ClientApi::SetCwdNoReload( const StrPtr * ) .....	48
Notes .....	48
Example .....	48
ClientApi::SetCwdNoReload( const char * ) .....	49
Notes .....	49
Example .....	49
ClientApi::SetHost( const StrPtr * ) .....	50
Notes .....	50
Example .....	50
ClientApi::SetHost( const char * ) .....	51
Notes .....	51
Example .....	51
ClientApi::SetIgnoreFile( const StrPtr * ) .....	52
Notes .....	52
See also .....	52
Example .....	52
ClientApi::SetIgnoreFile( const char * ) .....	53
Notes .....	53
See also .....	53
Example .....	53
ClientApi::SetPassword( const StrPtr * ) .....	54
Notes .....	54
Example .....	54
ClientApi::SetPassword( const char * ) .....	55
Notes .....	55
Example .....	55
ClientApi::SetPort( const StrPtr * ) .....	56
Notes .....	56
Example .....	56
ClientApi::SetPort( const char * ) .....	57
Notes .....	57
Example .....	57
ClientApi::SetProg( const StrPtr * ) .....	58
Notes .....	58
See also .....	58
Example .....	58
ClientApi::SetProg( const char * ) .....	59
Notes .....	59
See also .....	59
Example .....	59
ClientApi::SetProtocol( char *, char * ) .....	60
Notes .....	60
Example .....	61
ClientApi::SetProtocolV( char * ) .....	63
Notes .....	63
Example .....	63
ClientApi::SetTicketFile( const StrPtr * ) .....	64
Notes .....	64
Example .....	64

ClientApi::SetTicketFile( const char * ) .....	65
Notes .....	65
Example .....	65
ClientApi::SetUi( ClientUser * ) .....	66
Notes .....	66
Example .....	66
ClientApi::SetUser( const StrPtr * ) .....	67
Notes .....	67
Example .....	67
ClientApi::SetUser( const char * ) .....	68
Notes .....	68
Example .....	68
ClientApi::SetVersion( const StrPtr * ) .....	69
Notes .....	69
See also .....	69
Example .....	69
ClientApi::SetVersion( const char * ) .....	70
Notes .....	70
See also .....	70
Example .....	70
ClientProgress methods .....	71
ClientProgress::Description( const StrPtr *, int ) .....	71
Notes .....	71
See also .....	71
Example .....	71
ClientProgress::Done( int ) .....	72
Notes .....	72
See also .....	72
Example .....	72
ClientProgress::Total( long ) .....	73
Notes .....	73
See also .....	73
Example .....	73
ClientProgress::Update( long ) .....	74
Notes .....	74
See also .....	74
Example .....	74
ClientUser methods .....	75
ClientUser::CreateProgress( int ) .....	75
Notes .....	75
See also .....	75
ClientUser::Diff( FileSys *, FileSys *, int, char *, Error * ) .....	76
Notes .....	76
See also .....	76
Example .....	76
ClientUser::Diff( FileSys *, FileSys *, FileSys *, int, char *, Error * ) .....	78
Notes .....	78
ClientUser::Edit( FileSys *, Error * ) .....	79
Notes .....	79
Example .....	79
ClientUser::ErrorPause( char *, Error * ) .....	80

Notes .....	80
Example .....	80
ClientUser::File( FileSysType ) .....	81
Notes .....	81
Example .....	81
ClientUser::Finished() .....	82
Notes .....	82
Example .....	82
ClientUser::HandleError( Error * ) .....	83
Notes .....	83
Example .....	83
ClientUser::Help( const char *const * ) .....	84
Notes .....	84
Example .....	84
ClientUser::InputData( StrBuf *, Error * ) .....	85
Notes .....	85
Example .....	85
ClientUser::Merge( FileSys *, FileSys *, FileSys *, FileSys *, Error * ) .....	86
Notes .....	86
See also .....	86
Example .....	86
ClientUser::Message( Error * ) .....	88
Notes .....	88
Example .....	88
ClientUser::OutputBinary( const char *, int ) .....	89
Notes .....	89
Example .....	89
ClientUser::OutputError( const char * ) .....	90
Notes .....	90
Example .....	90
ClientUser::OutputInfo( char, const char * ) .....	91
Notes .....	91
Example .....	91
ClientUser::OutputStat( StrDict * ) .....	93
Notes .....	93
Example .....	93
ClientUser::OutputText( const char *, int ) .....	95
Notes .....	95
Example .....	95
ClientUser::ProgressIndicator() .....	96
Notes .....	96
See also .....	96
Example .....	96
ClientUser::Prompt( const StrPtr &, StrBuf &, int, Error * ) .....	97
Notes .....	97
Example .....	97
ClientUser::RunCmd( const char *, const char *, [...], Error * ) .....	98
Notes .....	98
Example .....	98
Error methods .....	100
Error::Clear() .....	100



Notes .....	100
Example .....	100
Error::Dump( const char * ) .....	101
Notes .....	101
Example .....	101
Error::Fmt( StrBuf * ) .....	102
Notes .....	102
Example .....	102
Error::Fmt( StrBuf *, int ) .....	103
Notes .....	103
Example .....	103
Error::GetGeneric() .....	105
Notes .....	105
Example .....	105
Error::GetSeverity() .....	106
Notes .....	106
Example .....	106
Error::IsFatal() .....	107
Notes .....	107
Example .....	107
Error::IsWarning() .....	108
Notes .....	108
Example .....	108
Error::Net( const char *, const char * ) .....	109
Notes .....	109
Example .....	109
Error::operator << ( int ) .....	110
Notes .....	110
Example .....	110
Error::operator << ( char * ) .....	111
Notes .....	111
Example .....	111
Error::operator << ( const StrPtr & ) .....	112
Notes .....	112
Error::operator = ( Error & ) .....	113
Notes .....	113
Example .....	113
Error::Set( enum ErrorSeverity, const char * ) .....	114
Notes .....	114
Example .....	114
Error::Set( ErrorId & ) .....	115
Notes .....	115
Error::Sys( const char *, const char * ) .....	116
Notes .....	116
Example .....	116
Error::Test() .....	117
Notes .....	117
Example .....	117
ErrorLog methods .....	118
ErrorLog::Abort() .....	118
Notes .....	118

Example .....	118
ErrorLog::Report() .....	119
Notes .....	119
Example .....	119
ErrorLog::SetLog( const char * ) .....	120
Notes .....	120
Example .....	120
ErrorLog::SetSyslog() .....	121
Notes .....	121
Example .....	121
ErrorLog::SetTag( const char * ) .....	122
Notes .....	122
Example .....	122
ErrorLog::UnsetSyslog() .....	123
Notes .....	123
Example .....	123
FileSys methods .....	124
FileSys::Chmod( FilePerm, Error * ) .....	124
Notes .....	124
Example .....	124
FileSys::Close( Error * ) .....	126
Notes .....	126
Example .....	126
FileSys::Create( FileSysType ) .....	127
Notes .....	127
Example .....	127
FileSys::Open( FileOpenMode, Error * ) .....	128
Notes .....	128
Example .....	128
FileSys::Read( const char *, int, Error * ) .....	130
Notes .....	130
Example .....	130
FileSys::Rename( FileSys *, Error * ) .....	132
Notes .....	132
Example .....	132
FileSys::Set( const StrPtr * ) .....	133
Notes .....	133
Example .....	133
FileSys::Stat() .....	134
Notes .....	134
Example .....	134
FileSys::StatModTime() .....	136
Notes .....	136
Example .....	136
FileSys::Truncate() .....	137
Notes .....	137
FileSys::Unlink( Error * ) .....	138
Notes .....	138
Example .....	138
FileSys::Write( const char *, int, Error * ) .....	139
Notes .....	139

Example .....	139
Ignore methods .....	140
Ignore::Reject( const StrPtr &, const StrPtr & ) .....	140
Notes .....	140
Example .....	140
Ignore::RejectCheck( const StrPtr & ) .....	141
Notes .....	141
Example .....	141
KeepAlive methods .....	142
KeepAlive::IsAlive() .....	142
Notes .....	142
See also .....	142
Example .....	142
MapApi methods .....	144
MapApi::Clear() .....	144
Notes .....	144
MapApi::Count() .....	145
Notes .....	145
Example .....	145
MapApi::GetLeft( int ) .....	147
Notes .....	147
See also .....	147
Example .....	147
MapApi::GetRight( int ) .....	148
Notes .....	148
See also .....	148
Example .....	148
MapApi::GetType( int ) .....	149
Notes .....	149
See also .....	149
Example .....	149
MapApi::Insert( const StrPtr &, MapType ) .....	150
Notes .....	150
Example .....	150
MapApi::Insert( const StrPtr &, const StrPtr &, MapType ) .....	151
Notes .....	151
Example .....	151
MapApi::Join( MapApi *, MapApi * ) [static] .....	152
Notes .....	152
Example .....	152
MapApi::Join( MapApi *, MapDir, MapApi *, MapDir ) [static] .....	154
Notes .....	154
Example .....	154
MapApi::Translate( const StrPtr &, StrBuf&, MapDir ) .....	156
Notes .....	156
Examples .....	156
Options methods .....	157
Options::GetValue( char opt, int subopt ) .....	157
Notes .....	157
See also .....	157
Example .....	157

Options::operator[]( char opt ) .....	159
Notes .....	159
See also .....	159
Example .....	159
Options::Parse( int &, char ** &, const char *, int, const ErrorId &, Error * ) .....	161
Notes .....	161
See also .....	162
Example .....	162
Options::Parse( int &, StrPtr * &, const char *, int, const ErrorId &, Error * ) .....	166
Notes .....	166
See also .....	166
ServerHelperApi methods .....	167
ServerHelperApi::ClearProtocol() .....	167
Notes .....	167
ServerHelperApi::CloneFromRemote(int,const StrPtr*,ClientUser*,Error*) .....	168
Notes .....	168
See also .....	168
Example .....	169
ServerHelperApi::CloneFromRemote(int,const char*,ClientUser*,Error*) .....	170
Notes .....	170
ServerHelperApi::CopyConfiguration(ServerHelperApi*,ClientUser*,Error*) .....	171
Notes .....	171
Example .....	171
ServerHelperApi::Exists(ClientUser*,Error*) .....	172
Notes .....	172
Example .....	172
ServerHelperApi::GetCaseFlag() .....	173
Notes .....	173
See also .....	173
ServerHelperApi::GetClient() .....	174
Notes .....	174
ServerHelperApi::GetClient(Error*) .....	175
Notes .....	175
See also .....	175
Example .....	175
ServerHelperApi::GetDvcsDir() .....	176
Notes .....	176
ServerHelperApi::GetPort() .....	177
Notes .....	177
ServerHelperApi::GetProg() .....	178
Notes .....	178
See also .....	178
ServerHelperApi::GetQuiet() .....	179
Notes .....	179
ServerHelperApi::GetUnicode() .....	180
Notes .....	180
See also .....	180
ServerHelperApi::GetUser() .....	181
Notes .....	181
ServerHelperApi::GetVersion() .....	182
Notes .....	182

See also .....	182
ServerHelperApi::InitLocalServer(ClientUser*,Error*) .....	183
Notes .....	183
Example .....	183
ServerHelperApi::PrepareToCloneFilepath(ServerHelperApi*,const char*,ClientUser*,Error*) .....	184
Notes .....	184
See also .....	184
Example .....	184
ServerHelperApi::PrepareToCloneFilepath(ServerHelperApi*,const StrPtr*,ClientUser*,Error*) .....	185
Notes .....	185
ServerHelperApi::PrepareToCloneRemote(ServerHelperApi*,const char*,ClientUser*,Error*) .....	186
Notes .....	186
See also .....	186
Example .....	186
ServerHelperApi::PrepareToCloneRemote(ServerHelperApi*,const StrPtr*,ClientUser*,Error*) .....	187
Notes .....	187
See also .....	187
ServerHelperApi::SetCaseFlag(const char*,Error*) .....	188
Notes .....	188
See also .....	188
ServerHelperApi::SetCaseFlag(const StrPtr*,Error*) .....	189
Notes .....	189
ServerHelperApi::SetClient(const char*) .....	190
Notes .....	190
ServerHelperApi::SetClient(const StrPtr*) .....	191
Notes .....	191
ServerHelperApi::SetDefaultStream(const char*) .....	192
Notes .....	192
ServerHelperApi::SetDefaultStream(const StrPtr*) .....	193
Notes .....	193
ServerHelperApi::SetDvcsDir(const char*) .....	194
Notes .....	194
ServerHelperApi::SetDvcsDir(const StrPtr*) .....	195
Notes .....	195
ServerHelperApi::SetPort(const char*) .....	196
Notes .....	196
ServerHelperApi::SetPort(const StrPtr*) .....	197
Notes .....	197
ServerHelperApi::SetProg(const char*) .....	198
Notes .....	198
ServerHelperApi::SetProg(const StrPtr*) .....	199
Notes .....	199
ServerHelperApi::SetProtocol(const char*,const char*) .....	200
Notes .....	200
ServerHelperApi::SetProtocolV(const char*) .....	201
Notes .....	201
ServerHelperApi::SetQuiet() .....	202

Notes .....	202
ServerHelperApi::SetUnicode(int) .....	203
Notes .....	203
ServerHelperApi::SetUser(const char*) .....	204
Notes .....	204
ServerHelperApi::SetUser(const StrPtr*) .....	205
Notes .....	205
ServerHelperApi::SetVersion(const char*) .....	206
Notes .....	206
See also .....	206
ServerHelperApi::SetVersion(const StrPtr*) .....	207
Notes .....	207
Signaler methods .....	208
Signaler::Block() .....	208
Notes .....	208
See also .....	208
Example .....	208
Signaler::Catch() .....	209
Notes .....	209
See also .....	209
Example .....	209
Signaler::DeleteOnIntr( void * ) .....	210
See also .....	210
Example .....	211
Signaler::Intr() .....	212
Notes .....	212
Caveat .....	212
See also .....	212
Example .....	213
Signaler::OnIntr( SignalFunc, void * ) .....	215
Notes .....	215
See also .....	215
Example .....	216
Signaler::Signaler() (constructor) .....	217
Notes .....	217
See also .....	217
StrBuf methods .....	218
StrBuf::Alloc( int ) .....	218
Notes .....	218
Example .....	219
StrBuf::Append( const char * ) .....	220
Notes .....	220
Example .....	220
StrBuf::Append( const char *, int ) .....	221
Notes .....	221
Example .....	221
StrBuf::Append( const StrPtr * ) .....	223
Notes .....	223
Example .....	224
StrBuf::Clear() .....	226
Notes .....	226

See also .....	226
Example .....	226
StrBuf::StrBuf() (Constructor) .....	228
Notes .....	228
Example .....	228
StrBuf::StrBuf( const StrBuf & ) (Copy Constructor) .....	229
Notes .....	229
Example .....	229
StrBuf::~StrBuf() (Destructor) .....	230
Notes .....	230
Example .....	230
StrBuf::Extend( char ) .....	231
Notes .....	231
See also .....	231
Example .....	232
StrBuf::Extend( const char *, int ) .....	233
Notes .....	233
See also .....	233
Example .....	234
StrBuf::operator =( const char * ) .....	235
Notes .....	235
Example .....	235
StrBuf::operator =( const StrBuf & ) .....	236
Notes .....	236
Example .....	236
StrBuf::operator =( const StrPtr & ) .....	237
Notes .....	237
Example .....	237
StrBuf::operator =( const StrRef & ) .....	238
Notes .....	238
Example .....	238
StrBuf::operator <<( const char * ) .....	239
Notes .....	239
Example .....	239
StrBuf::operator <<( int ) .....	241
Notes .....	241
Example .....	241
StrBuf::operator <<( const StrPtr * ) .....	243
Notes .....	243
Example .....	243
StrBuf::operator <<( const StrPtr & ) .....	245
Notes .....	245
Example .....	246
StrBuf::Set( const char * ) .....	247
Notes .....	247
Example .....	247
StrBuf::Set( const char *, int ) .....	248
Notes .....	248
Example .....	248
StrBuf::Set( const StrPtr * ) .....	249
Notes .....	249

Example .....	249
StrBuf::Set( const StrPtr & ) .....	250
Notes .....	250
Example .....	250
StrBuf::StringInit() .....	252
Notes .....	252
See also .....	252
Example .....	253
StrBuf::Terminate() .....	255
Notes .....	255
Example .....	255
See also .....	255
Example .....	256
StrDict methods .....	257
StrDict::GetVar( const StrPtr & ) .....	257
Notes .....	257
Example .....	257
StrDict::GetVar( const char * ) .....	259
Notes .....	259
StrDict::GetVar( const char *, Error * ) .....	260
Notes .....	260
StrDict::GetVar( const StrPtr &, int ) .....	261
Notes .....	261
StrDict::GetVar( const StrPtr &, int, int ) .....	262
Notes .....	262
StrDict::GetVar( int, StrPtr &, StrPtr & ) .....	263
Notes .....	263
StrDict::Load( FILE * ) .....	264
Notes .....	264
Example .....	264
StrDict::Save( FILE * ) .....	265
Notes .....	265
Example .....	265
StrDict::SetArgv( int, char *const * ) .....	266
Notes .....	266
Example .....	266
StrNum methods .....	267
StrNum::StrNum( int ) (constructor) .....	267
Notes .....	267
Example .....	267
StrNum::Set( int ) .....	268
Notes .....	268
Example .....	268
StrOps methods .....	269
StrOps::Caps( StrBuf & ) .....	269
Example .....	269
StrOps::Dump( const StrPtr & ) .....	270
Notes .....	270
Example .....	270
StrOps::Expand( StrBuf &, StrPtr &, StrDict & ) .....	271
Notes .....	271



Example .....	271
StrOps::Expand2( StrBuf &, StrPtr &, StrDict & ) .....	272
Notes .....	272
Example .....	272
StrOps::Indent( StrBuf &, const StrPtr & ) .....	274
Notes .....	274
Example .....	274
StrOps::Lines( StrBuf &, char *[], int ) .....	275
Notes .....	275
Example .....	275
StrOps::Lower( StrBuf & ) .....	276
Notes .....	276
Example .....	276
StrOps::OtoX( const unsigned char *, int, StrBuf & ) .....	277
Notes .....	277
Example .....	277
StrOps::Replace( StrBuf &, const StrPtr &, const StrPtr &, const StrPtr & ) .....	278
Notes .....	278
Example .....	278
StrOps::Sub( StrPtr &, char, char ) .....	279
Notes .....	279
Example .....	279
StrOps::Upper( StrBuf & ) .....	280
Notes .....	280
Example .....	280
StrOps::Words( StrBuf &, const char *[], char *[], int ) .....	281
Notes .....	281
Example .....	281
StrOps::XtoO( char *, unsigned char *, int ) .....	282
Notes .....	282
Example .....	282
StrPtr methods .....	283
StrPtr::Atoi() .....	283
Notes .....	283
Example .....	283
StrPtr::CCompare( const StrPtr & ) .....	284
Notes .....	284
See also .....	284
Example .....	284
StrPtr::Compare( const StrPtr & ) .....	285
Notes .....	285
See also .....	285
Example .....	285
StrPtr::Contains( const StrPtr & ) .....	287
Notes .....	287
Example .....	287
StrPtr::Length() .....	288
Example .....	288
StrPtr::operator []( int ) .....	289
Notes .....	289
Example .....	289

StrPtr::operators ==, !=, >, <, <=, >= ( const char * ) .....	290
Notes .....	290
Example .....	290
StrPtr::operators ==, !=, >, <, <=, >= ( const StrPtr & ) .....	291
Notes .....	291
Example .....	291
StrPtr::Text() .....	292
Notes .....	292
Example .....	292
StrPtr::Value() .....	293
Notes .....	293
Example .....	293
StrPtr::XCompare( const StrPtr & ) .....	294
Notes .....	294
See also .....	294
Example .....	294
StrRef methods .....	295
StrRef::StrRef() (constructor) .....	295
Notes .....	295
StrRef::StrRef( const StrPtr & ) (constructor) .....	296
Notes .....	296
Example .....	296
StrRef::StrRef( const char * ) (constructor) .....	297
Notes .....	297
Example .....	297
StrRef::StrRef( const char * , int ) (constructor) .....	298
Notes .....	298
Example .....	298
StrRef::Null() .....	299
Notes .....	299
Example .....	299
StrRef::operator =( StrPtr & ) .....	300
Notes .....	300
Example .....	300
StrRef::operator =( char * ) .....	301
Notes .....	301
Example .....	301
StrRef::operator +=( int ) .....	302
Notes .....	302
Example .....	302
StrRef::Set( char * ) .....	303
Notes .....	303
Example .....	303
StrRef::Set( char * , int ) .....	304
Notes .....	304
Example .....	304
StrRef::Set( const StrPtr * ) .....	305
Notes .....	305
Example .....	305
StrRef::Set( const StrPtr & ) .....	306
Notes .....	306

Example .....	306
License Statements .....	307



# About This Manual

This guide contains details about using the Perforce C/C API to create applications that interact correctly with the Perforce server. Be sure to read the code in the API's header and C files in conjunction with this guide.

Interfaces for C/C++, Java, Perl, Ruby, Python, PHP, and other languages are available from our website:

<http://www.perforce.com/product/components/apis>

## Helix documentation

The following table lists and describes key documents for Helix users, developers, and administrators. For complete information see the following:

<http://www.perforce.com/documentation>

For specific information about...	See this documentation...
Introduction to version control concepts and workflows; Helix architecture, and related products.	<a href="#">Introducing Helix</a>
Using the command-line interface to perform software version management and codeline management; working with Helix streams; jobs, reporting, scripting, and more.	<a href="#">Helix Versioning Engine User Guide</a>
Basic workflows using P4V, the cross-platform Helix desktop client.	<a href="#">P4V User Guide</a>
Working with personal and shared servers and understanding the distributed versioning features of the Helix Versioning engine.	<a href="#">Using Helix for Distributed Versioning</a>
<b>p4</b> command line (reference).	<a href="#">P4 Command Reference</a> , <b>p4 help</b>
Installing and administering the Helix versioning engine, including user management, security settings.	<a href="#">Helix Versioning Engine Administrator Guide: Fundamentals</a>
Installing and configuring Helix servers (proxies, replicas, and edge servers) in a distributed environment.	<a href="#">Helix Versioning Engine Administrator Guide: Multi-site Deployment</a>
Helix plug-ins and integrations.	IDEs: <a href="#">Using IDE Plug-ins</a> Defect trackers: <a href="#">Defect Tracking Gateway Guide</a> Others: online help from the Helix menu or <a href="#">web site</a>

For specific information about...	See this documentation...
Developing custom Helix applications using the Helix C/C++ API.	<a href="#">C/C++ API User Guide</a>
Working with Helix in Ruby, Perl, Python, and PHP.	<a href="#">APIs for Scripting</a>

## Syntax conventions

Helix documentation uses the following syntax conventions to describe command line syntax.

Notation	Meaning
<code>literal</code>	Monospace font indicates a word or other notation that must be used in the command exactly as shown.
<i>italics</i>	Italics indicate a parameter for which you must supply specific information. For example, for a <i>serverid</i> parameter, you must supply the id of the server.
[ -f ]	Square brackets indicate that the enclosed elements are optional. Omit the brackets when you compose the command.  Elements that are not bracketed are required.
...	Ellipses (...) indicate that the preceding element can be repeated as often as needed.
<i>element1</i>   <i>element2</i>	A vertical bar (   ) indicates that either <i>element1</i> or <i>element2</i> is required.

## Please give us feedback

We are interested in receiving opinions on this manual from our users. In particular, we'd like to hear from users who have never used Perforce before. Does this guide teach the topic well? Please let us know what you think; we can be reached at [manual@perforce.com](mailto:manual@perforce.com).

If you need assistance, or wish to provide feedback about any of our products, contact [support@perforce.com](mailto:support@perforce.com).

## Release compatibility of the API

---

The Perforce C/C++ API is subject to change from release to release, and is not guaranteed to be source-code compatible from one release to the next. However, applications that you create using the API can run against previous releases of Perforce and will probably run against later releases of Perforce.

Support for specific features depends on the version of Perforce and the API that you use.

## Purpose of the API

---

The Perforce C/C++ API enables you to create applications that interact with end users, send commands to the Perforce server and process data returned from the versioning service. The API is a programmatic interface, and does not send commands directly to the server.

## Architecture of the API

---

The basic client session is managed by a C++ class called `ClientApi`. All user interaction is channeled through the `ClientUser` C++ class. The default methods of `ClientUser` implement the **p4** command line interface. To create custom client applications, create subclasses based on `ClientUser`.

## API files

---

The Perforce C/C++ API consists of header files, link libraries, and the reference implementation of the `ClientUser` class. Only the libraries are platform-specific.

The API is packaged as an archive or zip file. The source code for the libraries is proprietary and is not included. To download the API, go to the Perforce FTP site and download the file for your platform. For example, to obtain the OS X version using a Web browser, use the following URL:

[ftp://ftp.perforce.com/perforce/r15.1/bin.macosx105x86\\_64/](ftp://ftp.perforce.com/perforce/r15.1/bin.macosx105x86_64/)

and download `p4api.tgz`.

(Specific API files can vary from release to release, and so are not individually described here.)





## Compiling and linking Perforce applications

The following sections tell you how to build your application on the target platform.

To build `p4api.cc`, include `clientapi.h`, which includes all the necessary header files for the sample client application.

### Link order

The link libraries distributed with P4API must be linked explicitly in the following order.

- `libclient.a`
- `librpc.a`
- `libsupp.a`
- `libp4sslstub.a`

In the Windows distribution, these files are named `libclient.lib`, `librpc.lib`, `libsupp.lib`, and `libp4sslstub.lib` respectively.

### SSL support

The Perforce C/C++ API can be configured to support encrypted connections to the Perforce servers. To enable this support you must replace the bundled `libp4sslstub.a` (on Windows, `libp4sslstub.lib`) with copies of the OpenSSL libraries. (If you do not intend to use your application with a Perforce Server that supports encryption then you may simply compile the application with the supplied stub library.)

OpenSSL libraries are available from many sources; the most up-to-date is from <http://www.openssl.org/>.

### OpenSSL Library Version

We recommend keeping current with the latest minor version matching the version referenced in the Perforce C/C++ API file `librpc.a` (or `librpc.lib` on Windows). To see which version is referenced by the library, run the following command on UNIX variants or Macintosh:

```
strings librpc.a | grep ^OpenSSL
```

On Windows:

```
strings librpc.lib | findstr /B OpenSSL
```

This command will produce an output similar to the following:

```
OpenSSL 1.0.1p 9 Jul 2015
```

In this example, you would use the latest minor version of OpenSSL that matches version 1.0.1.

## Link order for SSL support

To enable SSL support, replace the stub with the `ssl` and `crypto` libraries from OpenSSL, resulting in the following link order:

- `libclient.a`
- `librpc.a`
- `libsupp.a`
- `libssl.a`
- `libcrypto.a`

On Windows, the `ssl` and `crypto` OpenSSL libraries are named `ssleay32.lib` and `libeay32.lib` respectively.

## Compiler support

### UNIX

For all UNIX platforms, you can use the **gcc** compiler to compile client applications with the Perforce C/C++ API.

Note that `clientapi.h` includes `stdhdrs.h`, which might attempt to set platform-specific defines. To ensure these defines are set properly, compile with the `-DOS_XXX` flag, where `XXX` is the platform name as specified by Perforce. (Use **p4 -V** to display the platform name; for example, for `LINUX52X86`, specify `-DOS_LINUX`.)

Some platforms require extra link libraries for sockets. Solaris requires the following compiler flags:

`-lsocket -lnsl`

### Linux

Some platforms require extra link libraries for runtime support. Linux requires the following compiler flag:

`-lrt`

### Windows

Using Microsoft Visual Studio (VC++), compile your client application with the following flags:

`/DOS_NT /MT /DCASE_INSENSITIVE`

For debugging, compile with the `/MTd` flag for multithreading. Do not compile with `/MD` or `/MDd`, because these flags can cause undefined behavior.

Link with the following libraries:

- `libcmt.lib`
- `oldnames.lib`

- kernel32.lib
- ws2\_32.lib
- advapi32.lib

## Sample Jamfile

The following example shows a Jamfile that can be used to build `p4api.cc`, a Perforce application. (The example that the API is installed in the `api` subdirectory.)

```
CFLAGS = -g -D_GNU_SOURCE ;
LINK = c ;OPTIM = ;
Main p4api : p4api.cc ;
ObjectHdrs p4api : api ;
LinkLibraries p4api : api/libclient.a api/librpc.a api/libsupp.a
                  api/libp4sslstub.a;
```

For more about **jam**, see [“Building with Jam” on page 5](#).

## Sample Makefile

The following is a GNU **make** file for building `p4api.cc`, a Perforce application. (The example assumes the API is installed in the `api` subdirectory.)

```
SOURCES = p4api.cc
INCLUDES = -Iapi
OBJECTS = ${SOURCES:.cc=.o}
LIBRARIES = api/libclient.a api/librpc.a api/libsupp.a
            api/libp4sslstub.a
BINARY = p4api
RM = /bin/rm -f

C = c
CFLAGS = -c -g -D_GNU_SOURCE
LINK = c
LINKFLAGS =

.cc.o :
    ${C} ${CFLAGS} $< ${INCLUDES}

${BINARY} : ${OBJECTS}
    ${LINK} -o ${BINARY} ${OBJECTS} ${LIBRARIES}

clean :
    - ${RM} ${OBJECTS} ${BINARY}
```

## Building with Jam

Jam is a build tool, similar in its role to the more familiar **make**. Jamfiles are to **jam** as makefiles are to **make**.

Jam is an Open Source project sponsored by Perforce Software. Jam documentation, source code, and links to precompiled binaries are available from the Jam product information page at:

<http://www.perforce.com/documentation/jam>

The P4API distribution contains the necessary header files (\*.h) and libraries (**libclient.a**, **librpc.a**, **libsupp.a**, **libp4sslstub.a**) required to compile and link a client application. The distribution also includes a sample application in C++, **p4api.cc**.

In general, the process is similar to most APIs: compile your application sources, then link them with the API libraries. The precise steps needed vary somewhat from platform to platform.

The sample application **p4api.cc** is a portable, minimal Perforce application, which we can use as an example. For purposes of this example, assume a Linux system.

Compile and link **p4api.cc** as follows:

```
$ cc -c -o p4api.o -D_GNU_SOURCE -O2 -DOS_LINUX -DOS_LINUX24 \  
> -DOS_LINUXX86 -DOS_LINUX24X86 -I. -Imsgs -Isupport -Isys p4api.cc  
  
$ gcc -o p4api p4api.o libclient.a librpc.a libsupp.a libp4sslstub.a
```

The preprocessor definitions (*-Ddefinition*) vary from platform to platform.

In order to build the example across a wide variety of platforms, the API distribution also contains two "Jamfiles" (**Jamrules** and **Jamfile**), that describe to how to build the sample application on each platform.

## Building the sample application

Once you have Jam on your system, you can use it to build the **p4api** application. On some platforms, **jam** needs an extra hint about the operating system version. For instance, on RedHat Linux 7.1, with a 2.4 linux kernel, use **OSVER=24**:

```
$ jam
Set OSVER to 42/52 [RedHat M.n], or 22/24 [uname -r M.n]

$ uname -r
2.4.2-2

$ jam -s OSVER=24
...found 121 target(s)...
...updating 2 target(s)...
C++ p4api.o
Link p4api
Chmod1 p4api
...updated 2 target(s)...

$ p4api info
User name: you
Client name: you:home:sunflower
Client host: sunflower
Client root: /home/you
Current directory: /home/you/tmp/p4api
Client address: 207.46.230.220:35012
Server address: sunflower:1674
Server root: /home/p4/root
Server date: 2009/09/24 12:15:39 PDT
Server version: P4D/LINUX22X86/2009.1/192489 (2009/04/12)
Server license: Your Company 10 users (expires 2010/02/10)
Server license-ip: 10.0.0.2
```

As shown in the example above, **jam** does not, by default, show the actual commands used in the build (unless one of them fails). To see the exact commands **jam** generates, use the `-o file` option. This causes **jam** to write the updating actions to *file*, suitable for execution by a shell.

To illustrate; first, invoke **jam clean** to undo the build:

```
$ jam -s OSVER=42 clean
...found 1 target(s)...
...updating 1 target(s)...
Clean clean
...updated 1 target(s)...
```

Then use **jam -o build\_sample** to create the build file:

```

$ jam -s OSVER=42 -o build_sample
...found 121 target(s)...
...updating 2 target(s)...
C++ p4api.o
Link p4api
Chmod1 p4api
...updated 2 target(s)...

$ cat build_sample

cc -c -o p4api.o -O2 -DOS_LINUX -DOS_LINUX42 -DOS_LINUXX86 \
-DOS_LINUX42X86 -I. -Imsgs -Isupport -Isys p4api.cc
gcc -o p4api p4api.o libclient.a librpc.a libsupp.a libp4sslstub.a
chmod 711 p4api

```

The generated `build_sample` can then be executed by a shell:

```
/bin/sh build_sample
```

to produce the executable, which you can test by running `p4api info` or most other Perforce commands:

```

$ p4api changes -m 1

Change 372 on 2002/09/23 by you@you:home:sunflower 'Building API'

```

As you can see, `p4api` is a usable full-featured command line Perforce client (very similar to the `p4` command). The example's functionality comes from the default implementation of the `ClientUser` class, linked from the `libclient.a` library and the rest of the library code, for which source code is not included. The source for the default implementation is provided in the P4API distribution as `clientuser.cc`.

## Sending commands to the versioning service

Perforce applications interact with the versioning service by:

1. Initializing a connection.
2. Sending commands.
3. Closing the connection.

The Perforce server does not maintain any kind of session identifier. The server identifies the sender of commands by its combination of Perforce user name and client workspace. Different processes that use the same combination of user and workspace are not distinguished by the Perforce server. To prevent processes from interfering with each other when submitting changelists, be sure to use separate client specifications for each process. If you need to create large numbers of processes, consider creating a cache of client specifications and serving them to processes as required.

## Perforce settings on the user's machine

To determine which server and depot are accessed and how files are mapped, the standard classes in the API observe the Perforce settings on the user's machine. Assuming the workstation is configured correctly, your application does not need to provide logic that specifies server, port, workspace, or user.

To override the user's settings, your application can call **Set** methods.

Settings take precedence as follows, highest to lowest:

1. Values set within a Perforce application
2. Values in configuration files (**P4CONFIG**)
3. Values set as environment variables at the operating system prompt
4. Variables residing in the registry (set using the **p4 set** or **p4 set -s** commands on Windows client machines)
5. Default values defined by Perforce software or gathered from the system

## Connecting to the server

To connect to the Perforce server for which the client computer is configured, your client application must call the [client.Init\(\)](#) method; for example:

```
client.Init( &e );
if ( e.Test() )
{
    printf("Failed to connect:\n" );
    ErrorLog::Abort(); // Displays the error and exits
}
printf( "Connected OK\n" );
```

Your program only needs to connect once. After connecting, the application can issue as many Perforce commands as required. If you intend to use tagged output, your program must call [client.SetProtocol\(\)](#) before calling [client.Init\(\)](#). For details about using tagged output, refer to ["Tagged data" on page 10](#).

## Displaying Perforce forms

Perforce client commands that collect a large amount of input from the user (such as **p4 branch**, **p4 change**, **p4 label**) use ASCII forms. To interact with your end user, your client application program can display Perforce ASCII forms such as changelists, client specification, and so on. To display a form and collect user input, call [ClientUser::Edit\(\)](#), which puts the form into a temporary file and invokes the text editor that is configured for the client machine.

All form-related commands accept the batch mode flags **-o** and **-i**:

- **-o** causes the form to be passed to [ClientUser::OutputInfo\(\)](#).
- **-i** causes the form to be read with [ClientUser::InputData\(\)](#).

These flags allow changes to the form to occur between separate invocations of the **p4** application, rather than during a single invocation. (For details about the `-o` and `-i` global options, see the [P4 Command Reference](#).)

All form-related commands can return a form descriptor. Your application can use this descriptor to parse forms into constituent variables and to format them from their constituent variables. The `specstring` protocol variable enables this support in the server. Form descriptors are best used with the `tag` protocol variable, which causes the form data to appear using `ClientUser::OutputStat()` rather than `OutputInfo()`.

Select the protocol with `ClientApi::SetProtocol()` as follows:

```
client.SetProtocol( "specstring", "" );
client.SetProtocol( "tag", "" );
```

To obtain the descriptor containing the results of the method call, your application must pass a `StrDict` object to `ClientUser::OutputStat()`. Your application can override the `OutputStat()` method in a class derived from `ClientUser`. The Perforce C/C++ API calls this derived method, passing it the output from the command.

## Sending commands

The following example illustrates how you set up arguments and execute the **p4 fstat** command on a file named **Jam.html**.

```
char file[] = "Jam.html";
char *filep = &file[0];
client.SetArgv( 1, &filep );
client.Run( "fstat", &ui );
```

For commands with more arguments, use an approach like the following:

```
char *argv[] = { "-C", "-l", 0, 0 };
int argc = 2;
char *file = "Jam.html";
argv[ argc++ ] = file;
client.SetArgv( argc, argv );
client.Run( "fstat", &ui );
```

## Processing data from the server

The Perforce server (release 99.2 and higher) can return tagged data (name-value pairs) for some commands. The following sections tell you how to handle tagged and untagged data.

### Tagged data

The following example shows data returned in tagged format by **p4 -Ztag clients** command. (The `-Z` flag specifies that tagged data is to be returned; this flag is unsupported and intended for debugging use.)



```

...client xyzy
...Update 972354556
...Access 970066832
...Owner gerry
...Host xyzy
...Description Created by gerry

```

To enable the Perforce server to return tagged data, your application must call `SetProtocol("tag", "  ")` before connecting to the server. To extract values from tagged data, use the `GetVars` method.

The following Perforce commands can return tagged output. A release number, when present, indicates the first Perforce server release that supports tagged output for the command.

<b>p4 add</b> (2005.2)	<b>p4 fixes</b> (2000.1)	<b>p4 protect -o</b>
<b>p4 branch -o</b>	<b>p4 group -o</b>	<b>p4 reviews</b> (2005.2)
<b>p4 branches</b>	<b>p4 groups</b> (2004.2)	<b>p4 reopen</b> (2005.2)
<b>p4 change -o</b> (2005.2)	<b>p4 have</b> (2005.2)	<b>p4 resolve</b> (2005.2)
<b>p4 changes</b>	<b>p4 info</b> (2003.2)	<b>p4 revert</b> (2005.2)
<b>p4 client -o</b>	<b>p4 integrate</b> (2005.2)	<b>p4 review</b> (2005.2)
<b>p4 clients</b>	<b>p4 job -o</b>	<b>p4 submit</b> (2005.2)
<b>p4 counter</b> (2005.2)	<b>p4 jobs</b>	<b>p4 sync</b> (2005.2)
<b>p4 counters</b> (2000.2)	<b>p4 jobspec -o</b>	<b>p4 trigger -o</b>
<b>p4 delete</b> (2005.2)	<b>p4 label -o</b>	<b>p4 typemap -o</b> (2000.1)
<b>p4 describe</b>	<b>p4 labels</b>	<b>p4 unlock</b> (2005.2)
<b>p4 depots</b> (2005.2)	<b>p4 labelsync</b> (2005.2)	<b>p4 user -o</b>
<b>p4 diff</b> (2005.2)	<b>p4 lock</b> (2005.2)	<b>p4 users</b>
<b>p4 diff2</b> (2004.2)	<b>p4 logger</b> (2000.2)	<b>p4 verify</b> (2005.2)
<b>p4 edit</b> (2005.2)	<b>p4 monitor</b> (2005.2)	<b>p4 where</b> (2004.2)
<b>p4 filelog</b>	<b>p4 obliterate</b> (2005.2)	<b>p4 fix</b> (2005.2)

The tagged output of some commands may have changed since the command's first appearance in this table. The output of **p4 resolve** and **p4 diff** are not fully tagged. For complete details, see the release notes:

<http://www.perforce.com/perforce/r16.2/user/p4apinotes.txt>

To obtain output in the form used by earlier revisions of Perforce, set the `api` variable according to the notes for [SetProtocol\(\)](#).

## Untagged Data

To handle untagged data, create a subclass of `ClientUser` for every type of data required and provide alternate implementations of [ClientUser::OutputInfo\(\)](#), [OutputBinary\(\)](#), [OutputText\(\)](#), and [OutputStat\(\)](#).

## Disconnecting from the server

After your application has finished interacting with the Perforce server, it must disconnect as illustrated below:

```
client.Final( &e );
e.Abort();
```

To ensure the application can exit successfully, make sure to call [ClientApi::Final\(\)](#) before calling the destructor.

## Performing file I/O

---

The default client file I/O implementation returns a `FileSys` object, which is described in `fileSys.h`. To intercept client workspace file I/O, replace the `FileSys` [\\*ClientUser::File\(\)](#) method by subclassing `ClientUser`.

The following example illustrates how you can override `FileSys`.

```

#include "p4/clientapi.h"
class MyFileSys : public FileSys {
public:

    MyFileSys();
    ~MyFileSys();

    virtual void    Open( FileOpenMode mode, Error *e );
    virtual void    Write( const char *buf, int len, Error *e );
    virtual int     Read( char *buf, int len, Error *e );
    virtual int     ReadLine( StrBuf *buf, Error *e );
    virtual void    Close( Error *e );
    virtual int     Stat();
    virtual int     StatModTime();
    virtual void    Truncate( Error *e );
    virtual void    Unlink( Error *e = 0 );
    virtual void    Rename( FileSys *target, Error *e );
    virtual void    Chmod( FilePerm perms, Error *e );

protected:
    int nchars;
};

MyFileSys::MyFileSys()
{
    nchars = 0;
}

MyFileSys::~MyFileSys()
{
    printf( "Number of characters transferred = %d\n", nchars );
}

void MyFileSys::Open( FileOpenMode mode, Error *e )
{
    printf( "In MyFileSys::Open()\n" );
}

void MyFileSys::Write( const char *buf, int len, Error *e )
{
    printf( "In MyFileSys::Write()\n" );
    printf( "%s", buf );
    nchars = nchars + len;
}

int MyFileSys::Read( char *buf, int len, Error *e )
{
    printf( "In MyFileSys::Read()\n" );
    return 0;
}

int MyFileSys::ReadLine( StrBuf *buf, Error *e )
{
    printf( "In MyFileSys::ReadLine()\n" );
    return 0;
}

```

```
void MyFileSys::Close( Error *e )
{
    printf( "In MyFileSys::Close()\n" );
}

int MyFileSys::Stat()
{
    printf( "In MyFileSys::Stat()\n" );
    return 0;
}

int MyFileSys::StatModTime()
{
    printf( "In MyFileSys::StatModTime()\n" );
    return 0;
}

void MyFileSys::Truncate( Error *e )
{
    printf( "In MyFileSys::Truncate()\n" );
}

void MyFileSys::Unlink( Error *e = 0 )
{
    printf( "In MyFileSys::Unlink()\n" );
}

void MyFileSys::Rename( FileSystem *target, Error *e )
{
    printf( "In MyFileSys::Rename()\n" );
}

void MyFileSys::Chmod( FilePerm perms, Error *e )
{
    printf( "In MyFileSys::Chmod()\n" );
}

class ClientUserSubclass : public ClientUser {
public:
    virtual FileSystem *File( FileSystemType type );
};

FileSystem *ClientUserSubclass::File( FileSystemType type )
{
    return new MyFileSys;
}
```

```

int main( int argc, char **argv )
{
    ClientUserSubclass ui;
    ClientApi client;
    Error e;

    char force[] = "-f";
    char file[] = "hello.c";
    char *args[2] = { &force[0], &file[0] };

    // Connect to server

    client.Init( &e );
    e.Abort();

    // Run the command "sync -f hello.c"

    client.SetArgv( 2, &args[0] );
    client.Run( "sync", &ui );

    // Close connection

    client.Final( &e );
    e.Abort();
    return 0;
}

```

The preceding program produces the following output when you run it.

```

% ls -l hello.c
-r--r--r--  1 member  team           41 Jul 30 16:57 hello.c
% cat hello.c
main()
{
    printf( "Hello World!\n" );
}
% samplefilesys
//depot/main/hello.c#1 - refreshing /work/main/hello.c
In MyFileSys::Stat()
In MyFileSys::Open()
In MyFileSys::Write()
main()
{
    printf( "Hello World!\n" );
}
In MyFileSys::Close()
Number of characters transferred = 41

```

## Handling errors

To encapsulate error handling in a maintainable way, subclass `ClientUser` at least once for every command you want to run and handle errors in the `HandleError()` method of the derived class.

To best handle the formatting of error text, parse the error text, looking for substrings of anticipated errors, and display the rest. For example:

```
void P4CmdFstat::HandleError(Error *e)
{
    StrBuf m;
    e->Fmt( &m );
    if ( strstr( m.Text(), "file(s) not in client view." ) )
        e->Clear();
    else if ( strstr( m.Text(), "no such file(s)" ) )
        e->Clear();
    else if ( strstr( m.Text(), "access denied" ) )
        e->Clear();
    else
        this->e = *e;
}
```

## Connection errors

If any error occurs when attempting to connect with the Perforce server, the [ClientApi::Init\(\)](#) method returns an error code in its **Error** parameter.

## Server errors

The [ClientApi::Final\(\)](#) method returns any I/O errors that occurred during [ClientApi::Run\(\)](#) in its **Error** parameter. [ClientApi::Final\(\)](#) returns a non-zero value if any I/O errors occurred or if [ClientUser::OutputError\(\)](#) was called (reporting server errors) during the command run.

To report errors generated by the server during an operation, your application can call the [ClientUser::HandleError\(\)](#) method. The default implementation of [HandleError\(\)](#) is to format the error message and call [ClientUser::OutputError\(\)](#), which, by default, writes the message to standard output. [HandleError\(\)](#) has access to the raw **Error** object, which can be examined with the methods defined in **error.h**. Prior to release 99.1, Perforce servers invoked [OutputError\(\)](#) directly with formatted error text.

## Class overviews

The following classes comprise the Perforce API. Public methods for these classes are documented in [Chapter 3, "Public Methods Reference" on page 21](#).

### ClientApi - Perforce server connections and commands

The **ClientApi** class represents a connection with the Perforce server.

Member functions in this class are used to establish and terminate the connection with the server, establish the settings and protocols to use while running commands, and run Perforce commands over the connection.

I/O is handled by a `ClientUser` object, and errors are captured in an `Error` object. A `ClientApi` object maintains information about client-side settings (`P4PORT`, etc.) and protocol information, such as the server version, and whether "tagged" output is enabled.

`ClientApi` does not include any virtual functions, and typically does not need to be subclassed.

Any Perforce command that is executed must be invoked through `ClientApi::Run()` after first opening a connection using `ClientApi::Init()`. A single connection can be used to invoke multiple commands by calling `Run()` multiple times after a single `Init()`; this approach provides faster performance than using multiple connections.

## ClientProgress - progress indicators for Perforce commands

The `ClientProgress` class introduced in 2012.2 provides a means to report on the progress of running commands; you can customize this behavior by subclassing `ClientUser` and `ClientProgress`.

In `ClientUser`, implement `ClientUser::CreateProgress()` and `ClientUser::ProgressIndicator()`. In `ClientProgress`, implement `ClientProgress::Description()`, `ClientProgress::Total()`, `ClientProgress::Update()`, and `ClientProgress::Done()`

The methods of your `ClientProgress` object will be called during the life of a server command. Usually, `Description()` is called first with a `description` and a `units` from the server; the units of measure apply to the `Total()` and `Update()` methods. `Total()` is called if there is a known upper bound to the number of units, while `Update()` is called from time to time as progress is made. If your `Update()` implementation returns non-zero, the API assumes the user has also attempted to cancel the operation. `Done()` is called last, with the `fail` argument being non-zero in case of failure. When the command is complete, the API destroys the object by calling the destructor.

Default implementations are used in the `p4` command-line client, and report on the progress of `p4 -I submit` and `p4 -I sync -q`.

## ClientUser - I/O for Perforce commands

The `ClientUser` class is used for all client-side input and output. This class implements methods that return output from the server to the user after a command is invoked, and gather input from the user when needed.

Member functions in this class are used to format and display server output, invoke external programs (such as text editors, diff tools, and merge tools), gather input for processing by the server, and to handle errors.

Customized functionality in a Perforce application is most typically implemented by subclassing `ClientUser`. In order to enable such customization, nearly all of `ClientUser`'s methods are virtual. The default implementations are used in the `p4` command-line client.

## Error - collect and report layered errors

Member functions in this class are used to store error messages, along with information about generic type and severity, format error messages into a form suitable for display to an end user, or marshal them into a form suitable for transferring over a network.

**Error** objects are used to collect information about errors that occur while running a Perforce command.

When a connection is opened with [ClientApi::Init\(\)](#), a reference to an **Error** object is passed as an argument to [Init\(\)](#). This **Error** object then accumulates any errors that occur; a single **Error** object can hold information about multiple errors. The **Error** can then be checked, and its contents reported if necessary.

Although **Error** itself does not provide any virtual methods that can be re-implemented, the manner in which errors are handled can be changed by re-implementing [ClientUser::HandleError\(\)](#). The default behavior for handling errors typically consists of simply formatting and displaying the messages, but **Error** objects maintain additional information, such as severity levels, which can be used to handle errors more intelligently.

## ErrorLog - output error messages

The **ErrorLog** class is used to report layered errors, either by displaying error messages to `stderr`, or by redirecting them to logfiles. On UNIX systems, error messages can also be directed to the `syslog` daemon.

## FileSys - Perforce file I/O

The **FileSys** class provides a platform-independent set of methods used to create, read and write files to disk.

You can intercept the file I/O and implement your own client workspace file access routines by replacing **FileSys** [\\*ClientUser::File\(\)](#) in a **ClientUser** subclass.

### Note

Replacing the existing I/O routines is non-trivial. Your replacement routines must handle all special cases, including cross-platform file issues.

Unless your application has highly specialized requirements, (for instance, performing all file I/O in memory rather than on disk), this approach is not recommended.

If you intend to replace [File\(\)](#), all of the virtual methods documented are required. The non virtual methods are not required and not documented.

## Ignore - support for rejecting files

The **Ignore** class has two methods, [Ignore::Reject\(\)](#) and [Ignore::RejectCheck\(\)](#). Both methods are used by applications to determine whether files destined to be opened for add will be rejected due to matching an entry in an ignore files.

## KeepAlive - support for client-side disconnection

The **KeepAlive** class has only one method, [KeepAlive::IsAlive\(\)](#). The method is used by applications to support client-side command termination.



## MapApi - logic for view mappings

The `MapApi` class allows a client application to duplicate the logic used by the server when interpreting and combining view mappings such as branch views, client views, and protections.

Each `MapApi` object represents a single mapping that is built by calling `MapApi::Insert()` to add new lines. A file can be translated through the mapping or tested for inclusion by calling `MapApi::Translate()`. Two `MapApi` objects may be combined into a single new `MapApi` object (for example, a client view and a protection table may be joined into a single mapping that represents all files in the client view that are included in the protection table) by calling `MapApi::Join()`.

## Options - parse and store command line options

The `Options` class encapsulates functions useful for parsing command line flags, and also provides a means of storing flag values.

Sample code is provided to illustrate how `Options::GetValue()` and `Options::Parse()` work together to parse command line options.

## ServerHelperApi - helper methods for creating personal servers

The `ServerHelperApi` class is used to create personal servers. This class is only necessary when initially creating a local server; once it is created you can use the standard `ClientApi` and `ClientUser` classes to operate against the server.

## Signaler - interrupt handling

The `Signaler` class enables the API programmer to register functions that are to be called when the client application receives an interrupt signal. The `Signaler` class maintains a list of registered functions and calls each one in turn.

By default, after all of the registered functions have been executed, the process exits, returning -1 to the operating system.

## StrBuf - string manipulation

The `StrBuf` class is the preferred general string manipulation class. This class manages the memory associated with a string, including allocating new memory or freeing old memory as required.

The `StrBuf` class is derived from the `StrPtr` class, and makes heavy use of the `buffer` and `length` members inherited from the `StrPtr` class. The `buffer` member of a `StrBuf` instance is a pointer to the first byte in the string. The `length` member of a `StrBuf` instance is the length of the string.

Most member functions maintain the string pointed to by the `buffer` member of a `StrBuf` as a null-terminated string. However, the `Clear` member function does not set the first byte of the string to a null byte, nor does the `Extend` member function append a null byte to an extended string. If you need to maintain a string as null-terminated when using the `Clear()` and `Extend()` member functions, follow the calls to `Clear()` and `Extend()` with calls to `Terminate()`.

A number of member functions move the string pointed to by a `StrBuf`'s buffer, and change the `buffer` member to point to the new location. For this reason, do not cache the pointer. Use [StrPtr::Text\(\)](#) whenever the pointer a `StrBuf`'s buffer is required.

## StrDict - field/value manipulation

The `StrDict` class provides a dictionary object of `StrPtr` s with a simple Get/Put interface. This class contains abstract methods and therefore cannot be instantiated, but its subclasses adhere to the basic interface documented here.

`ClientApi` is a descendant of `StrDict`; most notably, the [StrDict::SetArgv\(\)](#) method is used to set the arguments to a Perforce command before executing it with [ClientApi::Run\(\)](#).

The [ClientUser::OutputStat\(\)](#) method takes a `StrDict` as an argument; the `StrDict` methods are therefore necessary to process data with [OutputStat\(\)](#). Note that pulling information from a `StrDict` is typically easier than trying to parse the text given to [OutputInfo\(\)](#).

## StrNum - small numeric strings

The `StrNum` class, derived from `StrPtr`, is designed to hold a small string representing a number. Like a `StrBuf`, it handles its own memory. Unlike a `StrBuf`, it does not dynamically resize itself, and is limited to 24 characters, meaning that the largest number that can be represented by a `StrNum` is 99999999999999999999999999999999.

## StrOps - string operations

`StrOps` is a memberless class containing static methods for performing operations on strings.

## StrPtr - text operations

The `StrPtr` class is a very basic pointer/length pair used to represent text.

This class provides a number of methods for comparison and reporting, but it is not in itself very useful for storing data; the `StrBuf` child class is a more practical means of storing data, as it manages its own memory.

## StrRef - refer to existing strings

The `StrRef` class is a simple pointer/length pair representing a string. The `StrRef` class is derived from `StrPtr` and does not add a great deal of new functionality to that class, with the exception of methods that make the pointer mutable (and therefore usable), whereas a base `StrPtr` is read-only.

As its name suggests, a `StrRef` serves as a reference to existing data, as the class does not perform its own memory allocation. The `StrBuf` class is most useful when storing and manipulating existing strings.

## ClientApi methods

### ClientApi::DefineClient( const char \*, Error \* )

Sets **P4CLIENT** in the Windows registry and applies the setting immediately.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new <b>P4CLIENT</b> setting
	Error *e	an Error object
Returns	void	

### Notes

To make the new **P4CLIENT** setting apply to the next command executed with [Run\(\)](#), [DefineClient\(\)](#) sets the value in the registry and then calls [SetClient\(\)](#).

### Example

The following code illustrates how this method might be used to make a Windows client application start up with a default **P4CLIENT** setting.

```
client.Init( &e );
client.DefineClient( "default_workspace", &e );
```

## ClientApi::DefineHost( const char \*, Error \* )

Sets **P4HOST** in the Windows registry and applies the setting immediately.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new <b>P4HOST</b> setting
	Error *e	an Error object
Returns	void	

### Notes

To make the new **P4HOST** setting apply to the next command executed with [Run\(\)](#), [DefineHost\(\)](#) sets the value in the registry and then calls [SetHost\(\)](#).

### Example

The following code illustrates how this method might be used to make a Windows client application start up with a default **P4HOST** setting.

```
client.Init( &e );
client.DefineHost( "default_host", &e );
```

## ClientApi::DefineIgnoreFile( const char \*, Error \*)

Sets **P4IGNORE** in the Windows registry and applies the setting immediately.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new <b>P4IGNORE</b> setting
	Error *e	an Error object
Returns	void	

### Notes

To make the new **P4IGNORE** setting apply to the next command executed with [Run\(\)](#), [DefineIgnoreFile\(\)](#) sets the value in the registry and then calls [SetIgnoreFile\(\)](#).

### See also

[ClientApi::GetIgnore\(\)](#) [ClientApi::GetIgnoreFile\(\)](#) [ClientApi::SetIgnoreFile\(\)](#)

### Example

The following code illustrates how this method might be used to make a Windows client application start up with a default **P4IGNORE** setting.

```
# include "clientapi.h"

int main()
{
    ClientApi client;
    Error e;

    client.Init( &e );
    client.DefineIgnoreFile( ".p4ignore", &e );
}
```

## ClientApi::DefinePassword( const char \*, Error \* )

Sets **P4PASSWD** in the Windows registry and applies the setting immediately.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new <b>P4PASSWD</b> setting
	Error *e	an Error object
Returns	void	

### Notes

To make the new **P4PASSWD** setting apply to the next command executed with [Run\(\)](#), [DefinePassword\(\)](#) sets the value in the registry and then calls [SetPassword\(\)](#).

[DefinePassword\(\)](#) does *not* define a new server-side password for the user.

Call [DefinePassword\(\)](#) with either the plaintext password, or its MD5 hash

### Example

The following code illustrates how this method might be used to make a Windows client application start up with a default **P4PASSWD** setting.

```
client.Init( &e );
client.DefinePassword( "default_pass", &e );
```

## ClientApi::DefinePort( const char \*, Error \* )

Sets **P4PORT** in the Windows registry and applies the setting immediately.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new <b>P4PORT</b> setting
	Error *e	an Error object
Returns	void	

### Notes

In order to make the new **P4PORT** setting apply to the next client connection opened with [Init\(\)](#), [DefinePort\(\)](#) sets the value in the registry and then calls [SetPort\(\)](#).

### Example

The following code illustrates how this method might be used to make a Windows client application automatically set itself to access a backup server if the primary server fails to respond. (This example assumes the existence of a backup server that perfectly mirrors the primary server.)

```
client.Init( &e );

if ( e.IsFatal() )
{
    e.Clear();
    ui.OutputError( "No response from server - switching to backup!\n" );
    client.DefinePort( "backup:1666", &e );
    client.Init( &e );
}
```

The first command to which the primary server fails to respond results in the error message and the program reinitializing the client to point to the server at **backup:1666**. Subsequent commands do not display the warning because the new **P4PORT** value has been set in the registry.

## ClientApi::DefineUser( const char \*, Error \* )

Sets **P4USER** in the Windows registry and applies the setting immediately.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new <b>P4USER</b> setting
	Error *e	an Error object
Returns	void	

### Notes

To make the new **P4USER** setting apply to the next command executed with [Run\(\)](#), [DefineUser\(\)](#) sets the value in the registry and then calls [SetUser\(\)](#).

### Example

The following code illustrates how this method might be used to make a Windows client application start up with a default **P4USER** setting.

```
client.Init( &e );
client.DefineUser( "default_user", &e );
```



## ClientApi::Dropped()

Check if connection is no longer usable.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	None	
Returns	int	nonzero if the connection has dropped

### Notes

[Dropped\(\)](#) is usually called after [Run\(\)](#); it then checks whether the command completed successfully. If the [Init\(\)](#) is only followed by one [Run\(\)](#), as in `p4api.cc`, calling [Final\(\)](#) and then checking the `Error` is sufficient to see whether the connection was dropped. However, if you plan to make many calls to [Run\(\)](#) after one call to [Init\(\)](#), [Dropped\(\)](#) provides a way to check that the commands are completing without actually cleaning up the connection with [Final\(\)](#).

### Example

The [Dropped\(\)](#) method is useful if you want to reuse a client connection multiple times, and need to make sure that the connection is still alive.

For example, an application for stress-testing a Perforce server might run "**p4 have**" 10,000 times or until the connection dies:

```
ClientApi client;
MyClientUser ui; //this ClientUser subclass doesn't output anything.
Error e;

client.Init( &e );
int count = 0;
while ( !( client.Dropped() ) && count < 10000 )
{
    count++;
    client.Run( "have", &ui );
}
printf( "Checked have list %d times.\n", count );
client.Final( &e ); // Clean up connection.
```

If the [Dropped\(\)](#) result is true, the `while` loop ends. The actual error message remains inaccessible until after the call to [client.Final\(\)](#) to close the connection and store the error.

## ClientApi::Final( Error \* )

Close connection and return error count.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	Error *e	an Error object
Returns	int	final number of errors

### Notes

Call this method after you are finished using the `ClientApi` object in order to clean up the connection. Every call to [Init\(\)](#) must eventually be followed by exactly one call to [Final\(\)](#).

### Example

The following example is a slight modification of `p4api.cc`, and reports the number of errors before the program exits:

```
client.Init( &e );

client.SetArgv( argc - 2, argv + 2 );
client.Run( argv[1], &ui );

printf( "There were %d errors.\n", client.Final( &e ) );
```

## ClientApi::GetClient()

Get current client setting.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ClientApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> a reference to the client setting

### Notes

The return value of [GetClient\(\)](#) is a fixed reference to this `ClientApi` object's setting.

Assigning the return value to a `StrPtr` results in a `StrPtr` containing a `Text()` value that changes if the `ClientApi` object's client setting changes.

Assigning the return value to a `StrBuf` copies the text in its entirety for future access, rather than simply storing a reference to data that might change later.

Under some circumstances, [GetClient\(\)](#) calls [GetHost\(\)](#) and returns that value - specifically, if no suitable `P4CLIENT` value is available in the environment, or previously set with [SetClient\(\)](#). (This is why, under the Perforce client, client name defaults to the host name if not explicitly set.)

In some instances, [GetHost\(\)](#) does not return valid results until after a call to [Init\(\)](#) - see the [GetHost\(\)](#) documentation for details.

### Example

This example demonstrates the use of [GetClient\(\)](#) and the difference between `StrPtr`'s and `StrBuf`'s.

```
ClientApi client;
StrPtr p;
StrBuf b;

client.Init();
client.SetClient( "one" );
p = client.GetClient();
b = client.GetClient();
client.SetClient( "two" );

printf( "Current client %s = %s\n", client.GetClient().Text(), p.Text() );
printf( "Previous client setting was %s\n", b.Text() );
```

Executing the preceding code produces the following output:

```
Current client two = two
Previous client setting was one
```

## ClientApi::GetConfig()

Get current configuration file.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ClientApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> a reference to the config file setting

### Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

If the **P4CONFIG** has not been set, [GetConfig\(\)](#) returns “noconfig”.

### Example

The following example demonstrates the usage of [GetConfig\(\)](#).

```
ClientApi client;
printf( "Current P4CONFIG is %s\n", client.GetConfig().Text() );
```

Executing the preceding code without having specified a configuration file produces the following output:

```
C:\perforce> a.out
Current P4CONFIG is noconfig
```

## ClientApi::GetCwd()

Get current working directory.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ClientApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> a reference to the name of the current directory

### Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

If the working directory has been set by a call to [SetCwd\(\)](#) or [SetCwdNoReload\(\)](#), subsequent calls to [GetCwd\(\)](#) return that setting regardless of the actual working directory.

### Example

The following example demonstrates the usage of [GetCwd\(\)](#).

```
ClientApi client;
printf( "Current directory is %s\n", client.GetCwd().Text() );
```

Executing the preceding code produces the following output:

```
C:\perforce> a.out
Current directory is c:\perforce
```

## ClientApi::GetHost()

Get client hostname.

Virtual?	No	Class
<a href="#">ClientApi</a>		Arguments
None		Returns

### Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

In some instances, [GetHost\(\)](#) is not valid until after the network connection has been established with [Init\(\)](#). [GetHost\(\)](#) attempts to pull its value from earlier [SetHost\(\)](#) calls, then from `P4HOST` in the environment, and then from the value of "hostname" returned by the client OS. If none of these is applicable, a reverse DNS lookup is performed, but the lookup will not work unless the connection has been established with [Init\(\)](#).

To guarantee valid results, call [GetHost\(\)](#) only after [Init\(\)](#) or [SetHost\(\)](#). As [GetHost\(\)](#) may sometimes be called during the execution of [GetClient\(\)](#), this warning applies to both methods.

As noted above, [GetHost\(\)](#) does not necessarily return the actual hostname of the machine if it has been overridden by `P4HOST` or an earlier call to [SetHost\(\)](#).

### Example

The following example demonstrates the usage of [GetHost\(\)](#).

```
ClientApi client;
client.Init();

printf( "Client hostname is %s\n", client.GetHost().Text() );
```

Executing the preceding code produces the following output:

```
shire% a.out
Client hostname is shire
```

## ClientApi::GetIgnore()

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	None	
Returns	Ignore *i	an <a href="#">Ignore</a> object, which can be used to determine if a path is ignored.

### Notes

If P4IGNORE is not set, no paths are ignored.

### See also

[ClientApi::DefineIgnoreFile\(\)](#) [ClientApi::GetIgnoreFile\(\)](#) [ClientApi::SetIgnoreFile\(\)](#)

### Example

This example demonstrates the use of [GetIgnore\(\)](#).

```
if ( client->GetIgnore()->Reject( *clientPath,
                                client->GetIgnoreFile() ) )
{
    /* handling for ignored file */
}
}
```

## ClientApi::GetIgnoreFile()

Get the full path name of the ignore file used for the current connection.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ClientApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> a reference to the path of the ignore file.

### Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

If the `P4IGNORE` is unset, [GetIgnoreFile\(\)](#) returns an uninitialized `StrPtr`.

### See also

[ClientApi::DefineIgnoreFile\(\)](#) [ClientApi::GetIgnore\(\)](#) [ClientApi::SetIgnoreFile\(\)](#)

### Example

This example demonstrates the use of [GetIgnoreFile\(\)](#).

```
# include "clientapi.h"

int main()
{
    ClientApi client;
    printf( "The current ignore file is '%s'\n",
           client.GetIgnoreFile().Text() );
}
```

Executing the preceding code produces output similar to the following:

```
The current ignore file is .p4ignore
```



## ClientApi::GetOs()

Get name of client operating system.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ClientApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> a reference to the OS string

### Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

[GetOs\(\)](#) returns one of "UNIX", "vms", "NT", "Mac", or null.

### Example

The following example demonstrates the usage of [GetOs\(\)](#).

```
ClientApi client;
printf( "Client OS is %s\n", client.GetOs().Text() );
```

Executing the preceding code under Windows produces the following output:

```
C:\perforce> a.out
Client OS is NT
```

Executing the preceding code on a UNIX machine produces the following output:

```
shire$ a.out
Client OS is UNIX
```

## ClientApi::GetPassword()

Get password setting.

Virtual?	No
Class	<a href="#">ClientApi</a>
Arguments	None
Returns	const StrPtr & a reference to the password

### Notes

See [GetClient\(\)](#) for more about the StrPtr return value.

This method returns the password currently set on the client, which may or may not be the one set on the server for this user. The command "**p4 passwd**" sets **P4PASSWD** on the client machine to an MD5 hash of the actual password, in which case [GetPassword\(\)](#) returns this MD5 hash rather than the plaintext version.

However, if the user sets **P4PASSWD** directly with the plaintext version, [GetPassword\(\)](#) returns that plaintext version. In both instances, the result is the same as that displayed by "**p4 set**" or an equivalent command that displays the value of the **P4PASSWD** environment variable.

[SetPassword\(\)](#) overrides the **P4PASSWD** value, and subsequent [GetPassword\(\)](#) calls return the new value set by [SetPassword\(\)](#) rather than the one in the environment.

### Example

The following example demonstrates the usage of [GetPassword\(\)](#).

```
ClientApi client;
printf( "Your password is %s\n", client.GetPassword().Text() );
```

The following session illustrates the effect of password settings on [GetPassword\(\)](#):

```
> p4 set P4PASSWD=p455w04d
> a.out
Your password is p455w04d

> p4 passwd
Enter new password:
Re-enter new password:
Password updated.

> a.out
Your password is 6F577E10961C8F7B519501097131787C
```

## ClientApi::GetPort()

Get current port setting.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ClientApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> a reference to the port setting

### Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

If the environment variable `P4PORT` is unset, [GetPort\(\)](#) sets the port to the default value of `perforce:1666`.

### Example

The following example demonstrates the usage of [GetPort\(\)](#).

```
ClientApi client;

printf( "You're looking for a server at %s\n", \
        client.GetPort().Text() );
```

Executing the preceding code produces the following output:

```
You're looking for a server at perforce:1666
```

## ClientApi::GetProtocol( const char \* )

Get protocol information for this connection.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ClientApi</a>	
<b>Arguments</b>	<code>const char *v</code>	the name of the protocol variable being checked
<b>Returns</b>	<code>StrPtr *</code>	a pointer to the variable's value

### Notes

If the variable is unset, the return value is null. If there is a value, it will be a number in most cases, but in the form of a `StrPtr` rather than an `int`.

Call [GetProtocol\(\)](#) only after a call to [Run\(\)](#), because protocol information is not available until after a call to [Run\(\)](#). Calling [GetProtocol\(\)](#) before [Run\(\)](#) results in a return value of `null`, which looks misleadingly like an indication that the variable is unset.

[GetProtocol\(\)](#) reports only on variables set by the server, not variables set by the client with calls to [SetProtocol\(\)](#).

### Example

The following example code checks whether the server is case-sensitive.

```

...
client.Init( &e );
...
client.Run();

if ( client.Dropped() )
{
    client.Final( &e );
}

if ( client.GetProtocol( "nocase" ) )
    printf( "Server case-insensitive.\n" );
else
    printf( "Server is case-sensitive.\n" );

```

## ClientApi::GetUser()

Get current user setting.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ClientApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> a reference to the user setting

### Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

### Example

The following example demonstrates the usage of [GetUser\(\)](#).

```
ClientApi client;
printf( "Your username is %s\n", client.GetUser().Text() );
```

Executing the preceding code as `testuser` produces the following output:

```
Your username is testuser
```

## ClientApi::Init( Error \* )

Establish a connection and prepare to run commands.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	Error *e	an Error object
Returns	void	

### Notes

[Init\(\)](#) must be called to establish a connection before any commands can be sent to the server. Each call to [Init\(\)](#) must be followed by exactly one call to [Final\(\)](#).

If an error occurs during [Init\(\)](#), it is most likely a connection error, with a severity of E\_FATAL.

### Example

The following code from `p4api.cc` opens a connection with [Init\(\)](#), sets arguments, runs a command, and closes the connection with [Final\(\)](#).

```
ClientUser ui;
ClientApi client;
Error e;

client.Init( &e );

client.SetArgv( argc - 2, argv + 2 );
client.Run( argv[1], &ui );
client.Final( &e );
return 0;
```

## ClientApi::Run( const char \*, ClientUser \* )

Run a Perforce command and return when it completes.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ClientApi</a>	
<b>Arguments</b>	<code>const char *func</code>	the name of the command to run
	<code>ClientUser *ui</code>	a pointer to a <code>ClientUser</code> object
<b>Returns</b>	<code>void</code>	

### Notes

The `func` argument to [Run\(\)](#) is the Perforce command to run, (for instance, `info` or `files`). Command arguments are not included and must be set separately with [StrDict::SetArgv\(\)](#).

Initialize the connection with [Init\(\)](#) before calling [Run\(\)](#), because without a connection, no commands can be sent to the server. Attempting to call [Run\(\)](#) before [Init\(\)](#) will probably result in a fatal runtime error.

[Run\(\)](#) returns only after the command completes. Note that all necessary calls to `ClientUser` methods are made during the execution of [Run\(\)](#), as dictated by the server.

### Example

The code below runs `p4 info`, using [ClientUser::OutputInfo\(\)](#) to display the results to the user. If a subclass of `ClientUser` is used here as the `ui` argument, that subclass's implementation of [OutputInfo\(\)](#) is used to display the results of the command.

```
ClientApi client;
ClientUser ui;
Error e;

client.Init( &e );
client.Run( "info", &ui );
client.Final( &e );
```

## ClientApi::SetBreak( KeepAlive \*breakCallback )

Establish a callback that is called every 0.5 seconds during command execution.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	KeepAlive *breakCallback	keepalive callback for user interrupt
Returns	void	

### Notes

To establish the callback routine, you must call [SetBreak\(\)](#) after [ClientApi::Init\(\)](#).

### See also

[KeepAlive::IsAlive\(\)](#)

### Example

The following example implements a custom [IsAlive\(\)](#) that can be called three times before returning 0 and terminating the connection. If the call to run the **changes** command takes less than 1.5 seconds to complete on the server side, the program outputs the list of changes. If the call to run the **changes** command takes more than 1.5 seconds, the connection is interrupted.



```
#include <clientapi.h>

// subclass KeepAlive to implement a customized IsAlive function.
class MyKeepAlive : public KeepAlive
{
    public:
    int IsAlive();
};

// Set up the interrupt callback. After being called 3 times,
// interrupt 3 times, interrupt the current server operation.
int MyKeepAlive::IsAlive()
{
    static int counter = 0;
    if ( ++counter > 3 )
    {
        counter = 0;
        return( 0 );
    }
    return( 1 );
}

// Now test the callback
ClientUser ui;
ClientApi client;
MyKeepAlive cb;
Error e;

client.Init( &e );
client.SetBreak( &cb ); // SetBreak must happen after the Init
client.Run( "changes", &ui );
client.Final( &e );
```

## ClientApi::SetClient( const StrPtr \* )

Sets the client setting to be used for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const StrPtr *c	the new client setting
Returns	void	

### Notes

[SetClient\(\)](#) does not permanently set the **P4CLIENT** value in the environment or registry. The new setting applies only to commands executed by calling this **ClientApi** object's [Run\(\)](#) method.

### Example

The following example displays two client specifications by calling [SetClient\(\)](#) between [Run\(\)](#) commands.

```
ClientApi client;
ClientUser ui;
StrBuf sb1;
StrBuf sb2;

sb1 = "client_one";
sb2 = "client_two";
args[0] = "-o";

client.SetClient( &sb1 );
client.SetArgv( 1, args );
client.Run( "client", &ui );

client.SetClient( &sb2 );
client.SetArgv( 1, args );
client.Run( "client", &ui );
```

## ClientApi::SetClient( const char \* )

Sets the client setting to be used for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new client setting
Returns	void	

### Notes

[SetClient\(\)](#) does not permanently set the **P4CLIENT** value in the environment or registry. The new setting applies only to commands executed by calling this **ClientApi** object's [Run\(\)](#) method.

### Example

The following example displays two client specifications by calling [SetClient\(\)](#) between [Run\(\)](#) commands.

```
ClientApi client;
ClientUser ui;

char *args[1];
args[0] = "-o";

client.SetClient( "client_one" );
client.SetArgv( 1, args );
client.Run( "client", &ui );

client.SetClient( "client_two" );
client.SetArgv( 1, args );
client.Run( "client", &ui );
```

## ClientApi::SetCwd( const StrPtr \* )

Sets the working directory to be used for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const StrPtr *c	the new directory path
Returns	void	

### Notes

[SetCwd\(\)](#) does not permanently set a new working directory in the client environment. The new setting applies only to commands executed by calling this `ClientApi` object's [Run\(\)](#) method.

### Example

The following code sets different working directories and displays them with **p4 info**.

```
ClientApi client;
ClientUser ui;
StrBuf sb1;
StrBuf sb2;

sb1 = "C:\one";
sb2 = "C:\two";

client.SetCwd( &sb1 );
client.Run( "info", &ui );

client.SetCwd( &sb2 );
client.Run( "info", &ui );
```

## ClientApi::SetCwd( const char \* )

Sets the working directory to be used for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new directory path
Returns	void	

### Notes

[SetCwd\(\)](#) does not permanently set a new working directory in the client environment. The new setting applies only to commands executed by calling this `ClientApi` object's [Run\(\)](#) method.

### Example

The following code sets different working directories and displays them with **p4 info**.

```
ClientApi client;
ClientUser ui;

client.SetCwd( "C:\one" );
client.Run( "info", &ui );

client.SetCwd( "C:\two" );
client.Run( "info", &ui );
```

## ClientApi::SetCwdNoReload( const StrPtr \* )

Sets the working directory to be used for this connection without checking **P4CONFIG**.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const StrPtr *c	the new directory path
Returns	void	

### Notes

[SetCwdNoReload\(\)](#) does not permanently set a new working directory in the client environment. The new setting applies only to commands executed by calling this `ClientApi` object's [Run\(\)](#) method.

Unlike [SetCwd\(\)](#), [SetCwdNoReload\(\)](#) ignores any **P4CONFIG** files found in the new directory hierarchy.

### Example

The following code sets different working directories and displays them with **p4 info**.

```
ClientApi client;
ClientUser ui;
StrBuf sb1;
StrBuf sb2;

sb1 = "C:\one";
sb2 = "C:\two";
client.SetCwdNoReload( &sb1 );
client.Run( "info", &ui );

client.SetCwdNoReload( &sb2 );
client.Run( "info", &ui );
```

## ClientApi::SetCwdNoReload( const char \* )

Sets the working directory to be used for this connection without checking **P4CONFIG**.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new directory path
Returns	void	

### Notes

[SetCwdNoReload\(\)](#) does not permanently set a new working directory in the client environment. The new setting applies only to commands executed by calling this `ClientApi` object's [Run\(\)](#) method.

Unlike [SetCwd\(\)](#), [SetCwdNoReload\(\)](#) ignores any **P4CONFIG** files found in the new directory hierarchy.

### Example

The following code sets different working directories and displays them with **p4 info**.

```
ClientApi client;
ClientUser ui;

client.SetCwdNoReload( "C:\one" );
client.Run( "info", &ui );

client.SetCwdNoReload( "C:\two" );
client.Run( "info", &ui );
```

## ClientApi::SetHost( const StrPtr \* )

Sets the hostname to be used for this connection.

Virtual?	No	Class
<a href="#">ClientApi</a>		Arguments
const StrPtr *c	the new hostname value	Returns

### Notes

[SetHost\(\)](#) does not permanently change the host name of the client or set **P4HOST** in the environment. The new setting applies only to commands executed by calling this **ClientApi** object's [Run\(\)](#) method.

### Example

The following example sets different hostnames and displays them with **p4 info**.

```
ClientApi client;
ClientUser ui;
StrBuf sb1;
StrBuf sb2;

sb1 = "magic";
sb2 = "shire";

client.SetHost( &sb1 );
client.Run( "info", &ui );

client.SetHost( &sb2 );
client.Run( "info", &ui );
```



## ClientApi::SetHost( const char \* )

Sets the hostname to be used for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new hostname value
Returns	void	

### Notes

[SetHost\(\)](#) does not permanently change the host name of the client or set **P4HOST** in the environment. The new setting applies only to commands executed by calling this **ClientApi** object's [Run\(\)](#) method.

### Example

The following example sets different hostnames and displays them with **p4 info**.

```
ClientApi client;
ClientUser ui;

client.SetHost( "magic" );
client.Run( "info", &ui );

client.SetHost( "shire" );
client.Run( "info", &ui );
```

## ClientApi::SetIgnoreFile( const StrPtr \* )

Sets the full path name of the ignore file to be used for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const StrPtr *c	the full path name of the new ignore file
Returns	void	

### Notes

[SetIgnoreFile\(\)](#) does not permanently set the **P4IGNORE** value in the environment or registry. The new setting applies only to commands executed by calling this `ClientApi` object's [Run\(\)](#) method.

### See also

[ClientApi::DefineIgnoreFile\(\)](#) [ClientApi::GetIgnore\(\)](#) [ClientApi::GetIgnoreFile\(\)](#)

### Example

The following example sets an ignore file location by calling [SetIgnoreFile\(\)](#).

```
# include "clientapi.h"

int main()
{
    ClientApi client;
    StrBuf sb;

    sb = ".p4ignore";
    client.SetIgnoreFile( &sb; );
}
```

## ClientApi::SetIgnoreFile( const char \* )

Sets the full path name of the ignore file to be used for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the full path name of the new ignore file
Returns	void	

### Notes

[SetIgnoreFile\(\)](#) does not permanently set the **P4IGNORE** value in the environment or registry. The new setting applies only to commands executed by calling this `ClientApi` object's [Run\(\)](#) method.

### See also

[ClientApi::DefineIgnoreFile\(\)](#) <<[clientapi.getignore](#),[ClientApi::GetIgnore\(\)](#)  
[ClientApi::GetIgnoreFile\(\)](#)

### Example

The following example sets a ticket file location by calling [SetIgnoreFile\(\)](#).

```
# include "clientapi.h"

int main()
{
    ClientApi client;

    client.SetIgnoreFile( ".p4ignore" );
}
```

## ClientApi::SetPassword( const StrPtr \* )

Sets the password to be used for this connection.

Virtual?	No	Class
<a href="#">ClientApi</a>		Arguments
const StrPtr *c	the new password value	Returns

### Notes

[SetPassword\(\)](#) does not permanently change the **P4PASSWORD** value in the environment, nor does it in any way change the password that has been set on the server. The new setting applies only to authentication attempts for commands executed by calling this **ClientApi** object's [Run\(\)](#) method.

### Example

The following trivial example demonstrates how to hard-code a password into an application without making it (immediately) user-visible.

```
ClientApi client;
ClientUser ui;
StrBuf sb;

sb = "p455w04d";

client.SetPassword( &sb );
client.SetArgv( argc - 2, argv + 2 );
client.Run( argv[1], &ui );
```

## ClientApi::SetPassword( const char \* )

Sets the password to be used for this connection.

Virtual?	No	Class
<a href="#">ClientApi</a>		Arguments
const char *c	the new password value	Returns

### Notes

[SetPassword\(\)](#) does not permanently change the **P4PASSWD** value in the environment, nor does it in any way change the password that has been set on the server. The new setting applies only to authentication attempts for commands executed by calling this **ClientApi** object's [Run\(\)](#) method.

### Example

The following trivial example demonstrates how to hard-code a password into an application without making it (immediately) user-visible.

```
ClientApi client;
ClientUser ui;

client.SetPassword( "p455w04d" );
client.SetArgv( argc - 2, argv + 2 );
client.Run( argv[1], &ui );
```

## ClientApi::SetPort( const StrPtr \* )

Sets the port to be used to open this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const StrPtr *c	the new port value
Returns	void	

### Notes

[SetPort\(\)](#) does not permanently change the **P4PORT** value in the environment. The new setting applies only to new connections established by calling this **ClientApi** object's [Init\(\)](#) method.

### Example

The following example demonstrates setting a new port value before initializing the connection.

```
ClientApi client;
Error e;
StrBuf sb;

sb = "ssl:magic:1666";

client.SetPort( &sb );
client.Init( &e );
```

## ClientApi::SetPort( const char \* )

Sets the port to be used to open this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new port value
Returns	void	

### Notes

[SetPort\(\)](#) does not permanently change the **P4PORT** value in the environment. The new setting applies only to new connections established by calling this **ClientApi** object's [Init\(\)](#) method.

### Example

The following example demonstrates setting a new port value before initializing the connection.

```
ClientApi client;
Error e;

client.SetPort( "magic:1666" );
client.Init( &e );
```

## ClientApi::SetProg( const StrPtr \* )

Sets the application or script name for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const StrPtr *c	the new program name
Returns	void	

### Notes

[SetProg\(\)](#) sets the identity of a client application as reported by the **p4 monitor** command, or as recorded by server logging.

Call [SetProg\(\)](#) before calling [Init\(\)](#).

### See also

[ClientApi::SetVersion\(\)](#)

### Example

The following example appears as **MyApp** in the output of **p4 monitor show**.

```
ClientApi client;
ClientUser ui;
StrBuf sb;
Error e;

sb.Set( "MyApp" );

client.Init( &e );
client.SetProg( &sb );
client.Run( "info", &ui );
```



## ClientApi::SetProg( const char \* )

Sets the application or script name for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new program name
Returns	void	

### Notes

[SetProg\(\)](#) sets the identity of a client application as reported by the **p4 monitor** command, or as recorded by server logging.

Call [SetProg\(\)](#) before calling [Init\(\)](#).

### See also

[ClientApi::SetVersion\(\)](#)

### Example

The following example appears as **MyApp** in the output of **p4 monitor show**.

```
ClientApi client;
ClientUser ui;
Error e;

client.Init( &e );
client.SetProg( "MyApp" );
client.Run( "info", &ui );
```

## ClientApi::SetProtocol( char \*, char \* )

Sets special protocols for the server to use.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	char *p	the name of the variable to set
	char *v	the new value for that variable
Returns	void	

### Notes

[SetProtocol\(\)](#) must be called before the connection is established with [Init\(\)](#).

The following variables are supported by [SetProtocol\(\)](#):

Variable	Meaning
tag	To enable tagged output (if tagged output for the command is supported by the server), set the <b>tag</b> variable to any value.
specstring	To enable specially formatted application forms, set the <b>specstring</b> to any value.
api	Set the <b>api</b> variable to the value corresponding to the level of server behavior your application supports.
enableStreams	To allow your application to work with stream depots, set the <b>enableStreams</b> variable to any value except 'no'. To explicitly disable streams support set <b>enableStreams</b> to 'no'.

By default, the value of the **api** protocol variable matches the version of the API with which you built your application; under most circumstances, you do not need to set the protocol version from within your application. If you are concerned about changes in server behavior, you can manually set the **api** variable in order to protect your code against such changes.

For instance, the "**p4 info**" command supports tagged output as of server release 2003.2, and changes to this format were made in 2004.2. Code requesting tagged output from "**p4 info**" that was compiled against the 2003.1 API library may break (that is, start producing tagged output) when running against a 2003.2 or newer server. To prevent this from happening, set **api** to the value corresponding to the desired server release.

Command	Set api to	Tagged output supported?
info	unset	Only if both server and API are at 2004.2 or greater

Command	Set api to	Tagged output supported?
<=55	Output is not tagged; behaves like 2003.1 or earlier, even if server supports tagged output.	=56
Output is tagged; behaves like 2003.2.	=57	Output is tagged; behaves like 2004.1, 2004.2, or 2005.1.

### Example

The following example demonstrates the use of [SetProtocol\(\)](#) to enable tagged output. The result of this call is that the `ClientUser` object uses [OutputStat\(\)](#) to handle the output, rather than [OutputInfo\(\)](#).

```
ClientApi client;
Error e;

client.SetProtocol( "tag", "" );
client.Init( &e );
client.Run( "branches", &ui );
client.Final( &e );
```

The following code illustrates how to ensure forward compatibility when compiling against newer versions of the Perforce API or connecting to newer Perforce servers.

```
ClientApi client;
Error e;

printf( "Output is tagged depending on API or server level.\n" );
client.SetProtocol( "tag", "" ); // request tagged output
client.Init( &e );
client.Run( "info", &ui );
client.Final( &e );

printf( "Force 2003.1 behavior regardless of API or server level.\n" );
client.SetProtocol( "tag", "" ); //request tagged output
client.SetProtocol( "api", "55" ); // but force 2003.1 mode (untagged)
client.Init( &e );
client.Run( "info", &ui );
client.Final( &e );

printf( "Request 2003.2 output if API and server support it.\n" );
client.SetProtocol( "tag", "" ); // request tagged output
client.SetProtocol( "api", "56" ); // force 2003.2 mode (tagged)
client.Init( &e );
client.Run( "info", &ui );
client.Final( &e );
```

The "**p4 info**" command supports tagged output only as of server release 2003.2. In the example, the first [Run\(\)](#) leaves `api` unset; if both the client API and Perforce server support tagged output for **p4 info** (that is, if you link this code with the 2003.2 or later API *and* run it against a 2003.2 or later server), the output is tagged. If you link the same code with the libraries from the 2003.1 release of the API, however, the first [Run\(\)](#) returns untagged output *even if connected to a 2003.2 server*. By setting `api` to 55, the second [Run\(\)](#) ensures 2003.1 behavior regardless of API or server level. The third call to [Run\(\)](#) supports 2003.2 behavior against a 2003.2 server and protects against future changes.

## ClientApi::SetProtocolV( char \* )

Sets special protocols for the server to use.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	char *nv	the name and value of the variable to set in <i>var=val</i> form
Returns	void	

### Notes

[SetProtocolV\(\)](#) functions identically to [SetProtocol\(\)](#), except that its argument is a single string of the format *variable=value*.

### Example

The following example demonstrates the use of [SetProtocolV\(\)](#) to enable tagged output. The result is that the `ClientUser` object uses [OutputStat\(\)](#) to handle the output, rather than [OutputInfo\(\)](#).

```
ClientApi client;
Error e;

client.SetProtocolV( "tag=" );
client.Init( &e );
client.Run( "branches", &ui );
client.Final( &e );
```

## ClientApi::SetTicketFile( const StrPtr \* )

Sets the full path name of the ticket file to be used for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const StrPtr *c	the full path name of the new ticket file
Returns	void	

### Notes

[SetTicketFile\(\)](#) does not permanently set the **P4TICKETS** value in the environment or registry. The new setting applies only to commands executed by calling this **ClientApi** object's [Run\(\)](#) method.

### Example

The following example sets a ticket file location by calling [SetTicketFile\(\)](#).

```
ClientApi client;
StrBuf sb;

sb = "/tmp/ticketfile.txt";
client.SetTicketFile( &sb );
```

## ClientApi::SetTicketFile( const char \* )

Sets the full path name of the ticket file to be used for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the full path name of the new ticket file
Returns	void	

### Notes

[SetTicketFile\(\)](#) does not permanently set the **P4TICKETS** value in the environment or registry. The new setting applies only to commands executed by calling this **ClientApi** object's [Run\(\)](#) method.

### Example

The following example sets a ticket file location by calling [SetTicketFile\(\)](#).

```
ClientApi client;

client.SetTicketFile( "/tmp/ticketfile.txt" );
```

## ClientApi::SetUi( ClientUser \* )

Reset the ClientUser object used for this connection.

Virtual?	No
Class	<a href="#">ClientApi</a>
Arguments	ClientUser *ui    a pointer to a ClientUser object.
Returns	void

### Notes

Unless you pass the ClientUser object to the [Run\(\)](#) method, you must first call [SetUi\(\)](#). The new setting applies to commands executed by calling this ClientApi object's [Run\(\)](#) method.

### Example

The following example illustrates two ways to run **p4 info**:

```
ClientApi client;
ClientUser ui;

client.Run( "info", &ui );

client.SetUi( &ui );
client.Run( "info" );
```



## ClientApi::SetUser( const StrPtr \* )

Sets the user for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const StrPtr *c	the new user name setting
Returns	void	

### Notes

[SetUser\(\)](#) does not permanently set the **P4USER** value in the environment or registry. Calling this method is equivalent to using the "-u" global option from the command line to set the user value for a single command, with the exception that a single **ClientApi** object can be used to invoke multiple commands in a row.

If the user setting is to be in effect for the command when it is executed, you must call [SetUser\(\)](#) before calling [Run\(\)](#).

### Example

The following example displays two user specifications by calling [SetUser\(\)](#) between [Run\(\)](#) commands.

```
ClientApi client;
Error e;
StrBuf sb1;
StrBuf sb2;

sb1 = "user1";
sb2 = "user2";

char *args[1];
args[0] = "-o";

client.SetUser( &sb1 );
client.SetArgv( 1, args );
client.Run( "user", &ui );

client.SetUser( &sb2 );
client.SetArgv( 1, args );
client.Run( "user", &ui );
```

## ClientApi::SetUser( const char \* )

Sets the user for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new user name setting
Returns	void	

### Notes

[SetUser\(\)](#) does not permanently set the **P4USER** value in the environment or registry. Calling this method is equivalent to using the "-u" global option from the command line to set the user value for a single command, with the exception that a single **ClientApi** object can be used to invoke multiple commands in a row.

If the user setting is to be in effect for the command when it is executed, you must call [SetUser\(\)](#) before calling [Run\(\)](#).

### Example

The following example displays two user specifications by calling [SetUser\(\)](#) between [Run\(\)](#) commands.

```
ClientApi client;
Error e;

char *args[1];
args[0] = "-o";

client.SetUser( "user1" );
client.SetArgv( 1, args );
client.Run( "user", &ui );

client.SetUser( "user2" );
client.SetArgv( 1, args );
client.Run( "user", &ui );
```

## ClientApi::SetVersion( const StrPtr \* )

Sets the application or script version for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const StrPtr *c	the new version number
Returns	void	

### Notes

[SetVersion\(\)](#) sets the version number of a client application as reported by the **p4 monitor -e** command, or as recorded by server logging.

If a client application compiled with version 2005.2 or later of the API does not call [SetVersion\(\)](#), then the version string reported by **p4 monitor -e** (and recorded in the server log) defaults to the api value appropriate for the server level as per [SetProtocol\(\)](#).

Call [SetVersion\(\)](#) after calling [Init\(\)](#) and before each call to [Run\(\)](#).

### See also

[ClientApi::SetProtocol\(\)](#) [ClientApi::SetProg\(\)](#)

### Example

The following example appears as **2005.2** in the output of **p4 monitor show -e**.

```
ClientApi client;
ClientUser ui;
StrBuf sb;
Error e;

sb.Set( "2005.2" );

client.Init( &e );
client.SetVersion( &sb );
client.Run( "info", &ui );
```

## ClientApi::SetVersion( const char \* )

Sets the application or script version for this connection.

Virtual?	No	
Class	<a href="#">ClientApi</a>	
Arguments	const char *c	the new version number
Returns	void	

### Notes

[SetVersion\(\)](#) sets the version number of a client application as reported by the **p4 monitor -e** command, or as recorded by server logging.

If a client application compiled with version 2005.2 or later of the API does not call [SetVersion\(\)](#), then the version string reported by **p4 monitor -e** (and recorded in the server log) defaults to the pass: [`<literal>api</literal>`] value appropriate for the server level as per [SetProtocol\(\)](#).

Call [SetVersion\(\)](#) after calling [Init\(\)](#) and before each call to [Run\(\)](#).

### See also

[ClientApi::SetProtocol\(\)](#) [ClientApi::SetProg\(\)](#)

### Example

The following example appears as **2005.2** in the output of **p4 monitor show -e**.

```
ClientApi client;
ClientUser ui;
Error e;

client.Init( &e );
client.SetVersion( "2005.2" );
client.Run( "info", &ui );
```

## ClientProgress methods

### ClientProgress::Description( const StrPtr \*, int )

Sets up a description and defines the units by which command progress is measured.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">ClientProgress</a>	
<b>Arguments</b>	<code>const StrPtr *desc</code>	description from the server
	<code>int units</code>	the units in which progress is to be measured
<b>Returns</b>	<code>void</code>	

### Notes

The API calls this method on command startup, supplying your implementation with a description and a client progress unit type. The `units` in which client progress is measured are defined in `clientprog.h` as follows:

Client Progress Unit	Value	Meaning
CPU_UNSPECIFIED	0	No units specified
CPU_PERCENT	1	Value is a percentage
CPU_FILES	2	Value is a count of files
CPU_KBYTES	3	Value is in kilobytes
CPU_MBYTES	4	Value is in megabytes

### See also

[ClientUser::CreateProgress\(\)](#) [ClientUser::ProgressIndicator\(\)](#) [ClientProgress::Done\(\)](#)  
[ClientProgress::Total\(\)](#) [ClientProgress::Update\(\)](#)

### Example

Create a subclass of `ClientProgress` and define an implementation of [Description\(\)](#), even if it is a trivial implementation:

```
void MyProgress::Description( const StrPtr *desc, int units )
{
    printf( "Starting command:\n" );
}
```

## ClientProgress::Done( int )

Called when an operation completes.

Virtual?	Yes	
Class	<a href="#">ClientProgress</a>	
Arguments	int fail	operation status: 1 if failed, 0 if successful
Returns	void	

### Notes

The API calls `Done()` on command completion with 0 for success, or 1 for failure.

### See also

[ClientUser::CreateProgress\(\)](#) [ClientUser::ProgressIndicator\(\)](#) [ClientProgress::Description\(\)](#)  
[ClientProgress::Total\(\)](#) [ClientProgress::Update\(\)](#)

### Example

To change the way completed actions are reported, create a subclass of `ClientProgress` and define an alternate implementation of `Done()`. For example, to output "Command failed" or "Command completed" upon success or failure, implement `Done()` as follows:

```
void MyProgress::Done( int fail )
{
    printf( fail ? "Command failed\n" : "Command completed\n");
}
```

## ClientProgress::Total( long )

Defines the number of units requested during the operation, if known.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">ClientProgress</a>	
<b>Arguments</b>	long units	Total number of client progress units expected, if known
<b>Returns</b>	void	

### Notes

The API calls this method if and when it has determined the number of client progress units, as defined by [Description\(\)](#), are to be processed during the command.

If the total number of expected units changes during the lifetime of a command, the API may call this method more than once. (The total number of expected units is *not* the same as the number of *remaining* units; certain commands may result in multiple calls to this method as the server determines more about the amount of data to be retrieved.)

### See also

[ClientUser::CreateProgress\(\)](#) [ClientUser::ProgressIndicator\(\)](#) [ClientProgress::Description\(\)](#)  
[ClientProgress::Done\(\)](#) [ClientProgress::Update\(\)](#)

### Example

To report how many progress units are expected, create a subclass of `ClientProgress` and define an alternate implementation of [Total\(\)](#).

For example, the following method outputs the number of units expected and is called when, if, and as the total number of expected units changes over the lifetime of the command:

```
void MyProgress::Total( long units )
{
    printf( "Now expecting %l units\n" );
}
```

## ClientProgress::Update( long )

Reports on command progress and user cancellation requests.

Virtual?	Yes	
Class	<a href="#">ClientProgress</a>	
Arguments	long units	Total number of progress units processed, if known
Returns	int	

### Notes

The API calls the [Update\(\)](#) method periodically during the life of a command and reports on the number of client progress units processed. (Because a million calls for an update of one million 1024-byte files would be prohibitive, not every unit of progress is reported.) Instead, the API calls this method periodically depending on a combination of elapsed time and number of client progress units processed.

In addition to reporting progress in terms of the units defined by [Description\(\)](#), if [Update\(\)](#) returns non-zero, the API interprets it as a user request to cancel the operation.

### See also

[ClientUser::CreateProgress\(\)](#) [ClientUser::ProgressIndicator\(\)](#) [ClientProgress::Description\(\)](#)  
[ClientProgress::Done\(\)](#) [ClientProgress::Total\(\)](#)

### Example

To report on units processed, create a subclass of `ClientProgress` and define an alternate implementation of [Update\(\)](#). A trivial implementation ignores cancel requests by always returning 0; a more useful implementation might resemble the following:

```
void MyProgress::Update( long units )
{
    if ( cancelclicked() ) // has anyone clicked the Cancel button?
    {
        return 1; // yes, user wishes to cancel
    }
    else
    {
        displayGUI( units ); // show how many units have been processed
        return 0; // user has not requested cancel, continue processing
    }
}
```



## ClientUser methods

### ClientUser::CreateProgress( int )

Create a [ClientProgress](#) object by subclassing, or null if no progress indicator is desired.

Virtual?	Yes	
Class	<a href="#">ClientUser</a>	
Arguments	int ProgressType	the type of progress to be reported
Returns	<a href="#">*ClientProgress</a>	a pointer to the new ClientProgress object.

### Notes

To enable progress reporting for a command, create a [ClientProgress](#) object and then implement [ProgressIndicator\(\)](#) to return 0 or 1 depending on whether or not you want to enable the progress indicator. (You typically implement [ProgressIndicator\(\)](#) to return 1, and call it only when a progress indicator is desired.)

The API calls this method with the appropriate **ProgressType** as defined in `clientprog.h`. The following **ProgressTypes** can be reported:

Client Progress Type	Value	Meaning
CPT_SENDFILE	1	Files sent to server
CPT_RECVFILE	2	Files received from server
CPT_FILESTRANS	3	Files transmitted
CPT_COMPUTATION	4	Computation performed server-side

### See also

[ClientUser::ProgressIndicator\(\)](#) [ClientProgress::Description\(\)](#) [ClientProgress::Done\(\)](#)  
[ClientProgress::Total\(\)](#) [ClientProgress::Update\(\)](#)

**ClientUser::Diff( FileSys \*, FileSys \*, int, char \*, Error \*)**

Diff two files, and display the results.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">ClientUser</a>	
<b>Arguments</b>	FileSys *f1	the first file to be diffed
	FileSys *f2	the second file to be diffed
	int doPage	should output be paged?
	char *diffFlags	flags to diff routine
	Error *e	an Error object
<b>Returns</b>	void	

**Notes**

This method is used by **p4 diff** and to display diffs from an interactive **p4 resolve**. If no external diff program is specified, the diff is carried out with a **Diff** object (part of the Perforce C/C++ API); otherwise, [Diff\(\)](#) simply calls the specified external program.

As with [Merge\(\)](#), the external program is invoked with [ClientUser::RunCmd\(\)](#).

If **doPage** is nonzero and the **P4PAGER** environment variable is set, the output is piped through the executable specified by **P4PAGER**.

**See also**

[ClientUser::RunCmd\(\)](#)

**Example**

In its default implementation, this method is called by an application when **p4 diff** is run. For example:

```
p4 diff -dc file.c
```

results in a call to [Diff\(\)](#) with the arguments:

Argument	Value
f1	a temp file containing the head revision of depot file <b>file.c</b>
f2	the local workspace version of file <b>file.c</b>

Argument	Value
doPage	0
diffFlag	c
e	a normal <code>Error</code> object

The diff is performed by creating a `Diff` object, giving it `f1` and `f2` as its inputs, and `-c` as its flag. The end result is sent to `stdout`. If either of the files is binary, the message “files differ” is printed instead.

Selecting the “d” option during an interactive `p4 resolve` also calls the `Diff()` method, with the `doPage` argument set to 1.

If the environment variable `P4PAGER` or `PAGER` is set, then setting `doPage` to 1 causes the diff output to be fed through the specified pager. If `P4PAGER` and `PAGER` are unset, `dopage` has no effect and the resolve routine displays the diff output normally.

To enable an application to override the default diff routine, create a subclass of `ClientUser` that overrides the `Diff()` method, and use this subclass in place of `ClientUser`.

As an example, suppose that you have a special diff program designed for handling binary files, and you want `p4 diff` to use it whenever asked to diff binary files (rather than display the default “files differ...”).

Furthermore, you want to keep your current `P4DIFF` setting for the purpose of diffing text files, so you decide to use a new environment variable called `P4DIFFBIN` to reference the binary diff program. If `P4DIFFBIN` is set and one of the files is non-text, the `P4DIFFBIN` program is invoked as `P4DIFF` is in the default implementation. Otherwise, the default implementation is called.

Most of the following code is copied and pasted from the default implementation.

```
MyClientUser::Diff( FileSystem *f1, FileSystem *f2, int doPage, char *df, Error *e )
{
    const char *diff = enviro->Get( "P4DIFFBIN" );
    if ( diff && ( !f1->IsTextual() || !f2->IsTextual() ) ) // binary diff
    {
        if ( !df || !*df )
        {
            RunCmd( diff, 0, f1->Name(), f2->Name(), 0, pager, e );
        }
        else
        {
            StrBuf flags;
            flags.Set( "-", 1 );
            flags << df;
            RunCmd( diff, flags.Text(), f1->Name(), f2->Name(), 0, pager, e );
        }
    }
    else ClientUser::Diff( f1, f2, doPage, df, e );
}
```

**ClientUser::Diff( FileSys \*, FileSys \*, FileSys \*, int, char \*, Error \* )**

Diff two files, and output the results to a third file.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">ClientUser</a>	
<b>Arguments</b>	FileSys *f1	the first file to be diffed
	FileSys *f2	the second file to be diffed
	FileSys *fout	the target file for diff output
	int doPage	should output be paged?
	char *diffFlags	flags to diff routine
	Error *e	an Error object
<b>Returns</b>	void	

**Notes**

This method works like [Diff\(\)](#), but instead of sending data to the standard output, writes the data to the specified output file.

## ClientUser::Edit( FileSys \*, Error \* )

Bring up the given file in a text editor. Called by all **p4** commands that edit specifications.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">ClientUser</a>	
<b>Arguments</b>	FileSys *f1	the file to be edited
	Error *e	an Error object
<b>Returns</b>	void	

### Notes

The FileSys \* argument to [Edit\(\)](#) refers to a client temp file that contains the specification that is to be given to the server. [Edit\(\)](#) does not send the file to the server; its only job is to modify the file. In the default implementation, [Edit\(\)](#) does not return until the editor has returned.

There is also a three-argument version of [Edit\(\)](#), for which the default two-argument version is simply a wrapper. The three-argument version takes an **Enviro** object as an additional argument, and the two-argument version simply passes the member variable **enviro** as this argument. Only the two-argument version is virtual.

### Example

The **p4 client** command is one of several Perforce commands that use [ClientUser::Edit\(\)](#) to allow the user to modify a specification. When the command is executed, the server sends the client specification to the client machine, where it is held in a temp file. [Edit\(\)](#) is then called with that file as an argument, and an editor is spawned. When the editor closes, [Edit\(\)](#) returns, and the temp file is sent to the server.

To allow modification of a specification by other means, such as a customized dialog or an automated process, create a subclass of **ClientUser** that overrides the [Edit\(\)](#) method and use this subclass in place of **ClientUser**.

Suppose that you have already written a function that takes a **FileSys** as input, opens a custom dialog, and returns when the file has been modified. Replace the body of [Edit\(\)](#) in your subclass with a call to your function, as follows:

```
void MyClientUser::Edit( FileSys *f1, Error *e )
{
    MyDialog( f1 );
}
```

## ClientUser::ErrorPause( char \*, Error \*)

Outputs an error and prompts for a keystroke to continue.

Virtual?	Yes	
Class	<a href="#">ClientUser</a>	
Arguments	char *errBuf	the error message to be printed
	Error *e	an Error object
Returns	void	

### Notes

The default implementation of [ErrorPause\(\)](#) consists solely of calls to [OutputError\(\)](#) and [Prompt\(\)](#).

### Example

One situation that results in a call to [ErrorPause\(\)](#) is an incorrectly edited specification; for example:

```
> p4 client
...
Error in client specification.
Error detected at line 31.
Wrong number of words for field 'Root'.
Hit return to continue...
```

In this instance, the first three lines of output were the `errBuf` argument to [ErrorPause\(\)](#); they were displayed using [OutputError\(\)](#).

To display an error and prompt for confirmation within a GUI application, create a subclass of `ClientUser` that overrides [ErrorPause\(\)](#) and use this subclass in place of `ClientUser`.

Suppose that you have a function `MyWarning()` that takes a `char *` as an argument, and displays the argument text in an appropriate popup dialog that has to be clicked to be dismissed. You can implement [ErrorPause\(\)](#) as a call to this function, as follows:

```
void MyClientUser::ErrorPause( char *errBuf, Error *e )
{
    MyWarning( errBuf );
}
```

Within a GUI, the warning text and "OK" button are probably bundled into a single dialog, so overriding [ErrorPause\(\)](#) is a better approach than overriding [OutputError\(\)](#) and [Prompt\(\)](#) separately.

## ClientUser::File( FileSysType )

Create a FileSys object for reading and writing files in the client workspace.

Virtual?	Yes	
Class	<a href="#">ClientUser</a>	
Arguments	FileSysType type	the file type of the file to be created
Returns	FileSys *	a pointer to the new FileSys.

### Notes

This method is a wrapper for FileSys::Create().

### Example

[ClientUser::File\(\)](#) is generally called whenever it's necessary to manipulate files in the client workspace. For example, a **p4 sync**, **p4 edit**, or **p4 revert** makes one call to [File\(\)](#) for each workspace file with which the command interacts.

An alternate implementation might return a subclass of FileSys. For example, if you have defined a class MyFileSys and want your MyClientUser class to use members of this class rather than the base FileSys, reimplement [File\(\)](#) to return a MyFileSys instead:

```
FileSys * MyClientUser::File( FileSysType type )
{
    return MyFileSys::Create( type );
}
```

## ClientUser::Finished()

Called after client commands finish.

<b>Virtual?</b>	Yes
<b>Class</b>	<a href="#">ClientUser</a>
<b>Arguments</b>	None
<b>Returns</b>	void

### Notes

This function is called by the server at the end of every Perform command, but in its default implementation, it has no effect. The default implementation of this function is empty - it takes nothing, does nothing, and returns nothing.

### Example

To trigger an event after the completion of a command, create a subclass of `ClientUser` and provide a new implementation of `Finished()` that calls that event.

For example, if you want your application to beep after each command, put the command into `Finished()`, as follows.

```
void MyClientUser::Finished()
{
    printf( "Finished!\n%c", 7 );
}
```



## ClientUser::HandleError( Error \* )

Process error data after a failed command.

Virtual?	Yes	
Class	<a href="#">ClientUser</a>	
Arguments	Error *e	an Error object
Returns	void	

### Notes

The default implementation formats the error with [Error::Fmt\(\)](#) and outputs the result with [OutputError\(\)](#).

2002.1 and newer servers do not call [HandleError\(\)](#) to display errors. Instead, they call [Message\(\)](#). The default implementation of [Message\(\)](#) calls [HandleError\(\)](#) if its argument is a genuine error; as a result, older code that uses [HandleError\(\)](#) can be used with the newer API and newer servers so long as the default implementation of [Message\(\)](#) is retained.

### Example

[HandleError\(\)](#) is called whenever a command encounters an error. For example:

```
> p4 files nonexistent
nonexistent - no such file(s).
```

In this case, the `Error` object given to [HandleError\(\)](#) contains the text "nonexistent - no such file(s)." and has a severity of 2 (`E_WARN`).

To handle errors in a different way, create a subclass of `ClientUser` with an alternate implementation of [HandleError\(\)](#).

For example, if you want an audible warning on a fatal error, implement [HandleError\(\)](#) as follows:

```
void MyClientUser::HandleError( Error *err )
{
    if ( err->IsFatal() ) printf ( "Fatal error!\n%c", 7 );
}
```

## ClientUser::Help( const char \*const \* )

Displays a block of help text to the user. Used by **p4 resolve** but not **p4 help**.

<b>Virtual?</b>	Yes
<b>Class</b>	<a href="#">ClientUser</a>
<b>Arguments</b>	<code>const char *const *help</code> an array of arrays containing the help text.
<b>Returns</b>	<code>void</code>

### Notes

This function is called by **p4 resolve** when the "?" option is selected during an interactive resolve. The default implementation displays the help text given to it, one line at a time.

### Example

The default implementation is called in order to display the "merge options" block of help text during a resolve by dumping the text to `stdout`.

To display the resolve help text in another manner, create a subclass of `ClientUser` with an alternate implementation of [Help\(\)](#).

For example, suppose you'd like a helpful message about the meaning of "yours" and "theirs" to be attached to the help message. Define the method as follows:

```
void MyClientUser::Help( const char *const *help )
{
    for ( ; *help; help++ )
        printf( "%s\n", *help );
    printf( "Note: In integrations, yours is the target file, \
          theirs is the source file.\n" );
}
```

## ClientUser::InputData( StrBuf \*, Error \* )

Provide data from `stdin` to `p4 < command> -i`.

Virtual?	Yes	
Class	<a href="#">ClientUser</a>	
Arguments	<code>StrBuf *strbuf</code>	the <code>StrBuf</code> which is to hold the data
	<code>Error *e</code>	an <code>Error</code> object
Returns	<code>void</code>	

### Notes

Any command that edits a specification can take the `-i` option; this method supplies the data for the specification. In the default implementation, the data comes from `stdin`, but an alternate implementation can accept the data from any source. This method is the only way to send a specification to the server without first putting it into a local file.

### Example

The default implementation is called during a normal invocation of `p4 client -i`.

**p4 client -i < clispec.txt**

In this example, `clispec.txt` is fed to the command as `stdin`. Its contents are appended to the `StrBuf` that is given as an argument to [InputData\(\)](#), and this `StrBuf` is given to the server after [InputData\(\)](#) returns.

To read the data from a different source, create a subclass of `ClientUser` with an alternate implementation of [InputData\(\)](#).

For example, suppose that you want to be able to edit a client specification without creating a local temp file. You've already written a function which generates the new client specification and stores it as a `StrBuf` variable in your `ClientUser` subclass. To send your modified client specification to the server when running `p4 client -i` with your modified `ClientUser`, implement [InputData\(\)](#) to read data from that `StrBuf`.

The example below assumes that the subclass `MyClientUser` has a variable called `mySpec` that already contains the valid client specification before running `p4 client -i`.

```
void MyClientUser::InputData( StrBuf *buf, Error *e )
{
    buf->Set( mySpec );
}
```

## ClientUser::Merge( FileSys \*, FileSys \*, FileSys \*, FileSys \*, Error \*)

Call an external merge program to merge three files during resolve.

Virtual?	Yes	
Class	<a href="#">ClientUser</a>	
Arguments	FileSys *base	the "base" file
	FileSys *leg1	the "theirs" file
	FileSys *leg2	the "yours" file
	FileSys *result	the final output file
	Error *e	an Error object
Returns	void	

### Notes

[Merge\(\)](#) is called if the "m" option is selected during an interactive resolve. [Merge\(\)](#) does not call the Perforce merge program; it merely invokes external merge programs (including P4Merge as well as third-party tools). External merge programs must be specified by an environment variable, either **P4MERGE** or **MERGE**. [Merge\(\)](#) returns after the external merge program exits.

As in [Diff\(\)](#), the external program is invoked using [ClientUser::RunCmd\(\)](#).

### See also

[ClientUser::RunCmd\(\)](#)

### Example

When the "merge" option is selected during an interactive resolve, the file arguments to [Merge\(\)](#) are as follows:

Argument	Value
base	A temp file built from the depot revision that is the "base" of the resolve.
leg1	A temp file built from the depot revision that is the "theirs" of the resolve.
leg2	The local workspace file that is the "yours" of the resolve.
result	A temp file in which to construct the new revision of "yours".

These file arguments correspond exactly to the command-line arguments passed to the merge tool.

After you "accept" the merged file (with "ae"), the "result" temp file is copied into the "leg2" or "yours" workspace file, and this is the file that is submitted to the depot.

To change the way that external merge programs are called during a resolve, create a subclass of `ClientUser` with an alternate implementation of `Merge()`.

For example, suppose that one of your favorite merge tools, "yourmerge", requires the "result" file as the first argument. Rather than wrapping the call to the merge tool in a script and requiring your users to set `P4MERGE` to point to the script, you might want to provide support for this tool from within your application as follows:

```
void MyClientUser::Merge(
    FileSys *base,
    FileSys *leg1,
    FileSys *leg2,
    FileSys *result,
    Error *e )
{
    char *merger;

    if ( !( merger = enviro->Get( "P4MERGE" ) ) &&
        !( merger = getenv( "MERGE" ) ) )
    {
        e->Set( ErrClient::NoMerger );
        return;
    }

    if ( strcmp( merger, "yourmerge" ) == 0 )
    {
        RunCmd( merger, result->Name(), base->Name(),
                leg1->Name(), leg2->Name(), 0, e );
    }
    else
    {
        RunCmd( merger, base->Name(), leg1->Name(),
                leg2->Name(), result->Name(), 0, e );
    }
}
```

## ClientUser::Message( Error \* )

Output information or errors.

Virtual?	Yes	
Class	<a href="#">ClientUser</a>	
Arguments	Error *e	an Error object containing the message
Returns	void	

### Notes

[Message\(\)](#) is used by 2002.1 and later servers to display information or errors resulting from Perforce commands. Earlier versions of the Perforce server call [OutputInfo\(\)](#) to display information, and [HandleError\(\)](#) to display errors.

The default implementation of [Message\(\)](#) makes calls to [OutputInfo\(\)](#) or [HandleError\(\)](#) as appropriate. If you want your application to be compatible with pre-2002.1 servers, use this default implementation of [Message\(\)](#) - newer servers will call [Message\(\)](#), and older servers will call [OutputInfo\(\)](#) and [HandleError\(\)](#) directly.

If you re-implement [Message\(\)](#) to handle errors and information in a different way, be advised that older servers will still call [OutputInfo\(\)](#) and [HandleError\(\)](#) rather than your [Message\(\)](#) method.

### Example

```
> p4 files //depot/proj/...
//depot/proj/file.c#1 - add change 456 (text)
```

In this example, the server passes a single **Error** object to the **ClientUser**'s [Message\(\)](#) method, with a severity of **E\_INFO** and text `//depot/proj/file.c#1 - add change 456 (text)`. The default [Message\(\)](#) method detects that this was an "info" message, and passes the text to [OutputInfo\(\)](#), which by default sends the text to **stdout**.

To handle messages differently, subclass **ClientUser** and re-implement the [Message\(\)](#) method (see the preceding note on interoperability with old servers if you do this).

For example, to take all server messages and load them into a **StrBuf** that is a member of your **ClientUser** class, use the following:

```
void MyClientUser::Message( Error *err )
{
    StrBuf buf;
    err->Fmt( buf, EF_PLAIN );
    myBuf.Append( buf );
}
```

## ClientUser::OutputBinary( const char \*, int )

Output binary data.

Virtual?	Yes	
Class	<a href="#">ClientUser</a>	
Arguments	const char *data	a pointer to the first byte of data to output
	int length	the number of bytes to output
Returns	void	

### Notes

The default implementation of [OutputBinary\(\)](#) writes the contents of a binary file to `stdout`. A call to [OutputBinary\(\)](#) is typically the result of running `p4 print` on a binary file:

```
p4 print //depot/file.jpg > newfile.jpg
```

### Example

To modify the way in which binary files are output with `p4 print`, create a subclass of `ClientUser` with an alternate implementation of [OutputBinary\(\)](#).

For example, suppose that you want PDF files to be printed to `stdout` as plain text. Add the following code (that checks to see if the file is PDF and, if so, calls a hypothetical `OutputPDF()` function to output PDFs to `stdout`) to the beginning of your implementation of [OutputBinary\(\)](#).

```
void MyClientUser::OutputBinary( const char *data, int length )
{
    static unsigned char pdfFlag[] = { '%', 'P', 'D', 'F', '-' };
    if ( length >= 5 && memcmp( data, pdfFlag, sizeof( pdfFlag ) ) )
        OutputPDF( data, length );
    else
        ClientUser::OutputBinary( data, length );
}
```

## ClientUser::OutputError( const char \* )

Display a message as an error.

Virtual?	Yes	
Class	<a href="#">ClientUser</a>	
Arguments	const char *errBuf	the error message
Returns	void	

### Notes

The default implementation sends its argument to `stderr`. [OutputError\(\)](#) is called by functions like [HandleError\(\)](#).

### Example

Because the default implementation of [HandleError\(\)](#) calls it, [OutputError\(\)](#) is responsible for printing every error message in Perforce. For example:

```
p4 files //nonexistent/...
nonexistent - no such file(s).
```

In this case, the argument to [OutputError\(\)](#) is the array containing the error message "nonexistent - no such file(s)."

To change the way error messages are displayed, create a subclass of `ClientUser` and define an alternate implementation of [OutputError\(\)](#).

For example, to print all error messages to `stdout` rather than `stderr`, and precede them with the phrase "!!ERROR!!", implement [OutputError\(\)](#) as follows:

```
void MyClientUser::OutputError( const char *errBuf )
{
    printf( "!!ERROR!! " );
    fwrite( errBuf, 1, strlen( errBuf ), stdout );
}
```



## ClientUser::OutputInfo( char, const char \* )

Output tabular data.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">ClientUser</a>	
<b>Arguments</b>	char level	the indentation "level" of the output
	const char *data	one line of output
<b>Returns</b>	void	

### Notes

[OutputInfo\(\)](#) is called by the server during most Perforce commands; its most common use is to display listings of information about files. Any output not printed with [OutputInfo\(\)](#) is typically printed with [OutputText\(\)](#). Running `p4 -s <command>` indicates whether any given line of output is "info" or "text".

In the default implementation of [OutputInfo\(\)](#), one "... " string is printed per "level". Values given as "levels" are either 0, 1, or 2. The "data" passed is generally one line, without a line break; [OutputInfo\(\)](#) adds the newline when it prints the output.

To capture information directly from Perforce commands for parsing or storing rather than output to `stdout`, it is usually necessary to use an alternate implementation of [OutputInfo\(\)](#).

2002.1 and newer servers do not call [OutputInfo\(\)](#) to display information. Instead, they call [Message\(\)](#). The default implementation of [Message\(\)](#) calls [OutputInfo\(\)](#) if its argument represents information instead of an error; older code that uses [OutputInfo\(\)](#) can be used with the newer API and newer servers, so long as the default implementation of [Message\(\)](#) is retained.

### Example

The `p4 filelog` command produces tabular output:

```
> p4 filelog final.c
//depot/final.c
... #3 change 703 edit on 2001/08/24 by testuser@shire (text) 'fixed'
... .. copy into //depot/new.c#4
... #2 change 698 edit on 2001/08/24 by testuser@shire (text) 'buggy'
... .. branch into //depot/middle.c#1
... #1 change 697 branch on 2001/08/24 by testuser@shire (text) 'test'
... .. branch from //depot/old.c#1,#3
```

Each line of output corresponds to one call to [OutputInfo\(\)](#). The first line of output has a level of '0', the line for each revision has a level of '1', and the integration record lines have levels of '2'. (The actual "data" text for these lines does not include the "... " strings.)

To alter the way in which "info" output from the server is handled, create a subclass of `ClientUser` and provide an alternate implementation of `OutputInfo()`.

For example, to capture output in a set of `StrBuf` variables rather than display it to `stdout`, your `ClientUser` subclass must contain three `StrBufs`, one for each level of info output, as follows:

```
void MyClientUser::OutputInfo( char level, const char *data )
{
    switch( level )
    {
        default:
        case '0':
            myInfo0.Append( data );
            myInfo0.Append( "\n" );
            break;
        case '1':
            myInfo1.Append( data );
            myInfo1.Append( "\n" );
            break;
        case '2':
            myInfo2.Append( data );
            myInfo2.Append( "\n" );
            break;
    }
}
```

## ClientUser::OutputStat( StrDict \* )

Process tagged output.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">ClientUser</a>	
<b>Arguments</b>	StrDict *varList	a StrDict containing the information returned by the command
<b>Returns</b>	void	

### Notes

Normally, the only Perforce command that sends output through [OutputStat\(\)](#) is **p4 fstat**, which always returns tagged output. Some other commands can be made to return tagged output by setting the "tag" protocol variable, in which case the output is in the form of a StrDict suitable for passing to [OutputStat\(\)](#) for processing.

It is generally easier to deal with tagged output than it is to parse standard output. The default implementation of [OutputStat\(\)](#) passes each variable/ value pair in the StrDict to [OutputInfo\(\)](#) as a line of text with a level of "1", with the exception of the "func" var, which it skips. Alternate implementations can use tagged output to extract the pieces of information desired from a given command.

### Example

Consider the following output from **p4 fstat**:

```
> p4 fstat file.c
... depotFile //depot/file.c
... clientFile c:\depot\file.c
... isMapped
... headAction integrate
... headType text
... headTime 998644337
... headRev 10
... headChange 681
... headModTime 998643970
... haveRev 10
```

The StrDict passed to [OutputStat\(\)](#) consists of eight variable/ value pairs, one for each line of output, plus a "func" entry, which is discarded by the default implementation of [OutputStat\(\)](#). Other commands can be made to return tagged output through [OutputStat\(\)](#) by using the -Ztag global option at the command line.

To process tagged output differently, create a subclass of **ClientUser** with an alternate implementation of [OutputStat\(\)](#). The following simple example demonstrates how the "headRev" and "haveRev" variables resulting from an "fstat" command can be easily extracted and manipulated.

Other commands provide `StrDicts` with different variable/value pairs that can be processed in similar ways; use **p4 -Ztag command** to get an understanding for what sort of information to expect.

```
void MyClientUser::OutputStat( StrDict *varList )
{
    StrPtr *headrev;
    StrPtr *haverev;

    headrev = varList->GetVar( "headRev" );
    haverev = varList->GetVar( "haveRev" );

    printf( "By default, revision numbers are returned as strings:\n" );
    printf( "  Head revision number: %s\n", headrev->Text() );
    printf( "  Have revision number: %s\n", haverev->Text() );

    printf( "but revision numbers can be converted to integers:\n" );
    printf( "  Head revision number: %d\n", headrev->Atoi() );
    printf( "  Have revision number: %d\n", haverev->Atoi() );
}
```

## ClientUser::OutputText( const char \*, int )

Output textual data.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">ClientUser</a>	
<b>Arguments</b>	const char *errBuf	the block of text to be printed
	int length	the length of the data
<b>Returns</b>	void	

### Notes

The most common usage of [OutputText\(\)](#) is in running **p4 print** on a text file.

### Example

```
> p4 print -q file.txt
This is a text file.
It is called "file.txt"
```

The arguments to [OutputText\(\)](#) in the preceding example are the pointer to the first character in the file contents, and the length of the file in bytes.

To alter the way in which [OutputText\(\)](#) handles text data, create a subclass of `ClientUser` and provide an alternate implementation of [OutputText\(\)](#).

For example, suppose that your `ClientUser` subclass contains a `StrBuf` called `myData`, and you want to store the data in this `StrBuf` rather than dump it to `stdout`.

```
void MyClientUser::OutputText( const char *data, int length )
{
    myData.Set( data, length );
}
```

## ClientUser::ProgressIndicator()

Returns nonzero if progress is to be reported, otherwise returns 0.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">ClientUser</a>	
<b>Arguments</b>	None	
<b>Returns</b>	int	returns non-zero if progress indicators are desired, 0 otherwise

### Notes

After you have created a [ClientProgress](#) object with [CreateProgress\(\)](#), you must also implement [ProgressIndicator\(\)](#) to return 0 or 1 depending on whether or not you want to report progress.

### See also

[ClientUser::CreateProgress\(\)](#) [ClientProgress::Description\(\)](#) [ClientProgress::Done\(\)](#)  
[ClientProgress::Total\(\)](#) [ClientProgress::Update\(\)](#)

### Example

The typical implementation of [ProgressIndicator\(\)](#) returns 1, and you call it when you wish to enable progress reporting:

```
MyUserProgress::ProgressIndicator()
{
    return 1;
}
```

## ClientUser::Prompt( const StrPtr &, StrBuf &, int, Error \* )

Prompt the user and get a response.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">ClientUser</a>	
<b>Arguments</b>	<code>const StrPtr &amp;msg</code>	the message with which to prompt the user
	<code>StrBuf &amp;rsp</code>	where to put the user's response
	<code>int noEcho</code>	specifies whether echo should be turned off at the console
	<code>Error *e</code>	an <code>Error</code> object
<b>Returns</b>	<code>void</code>	

### Notes

[Prompt\(\)](#) is used in the default implementation of [HandleError\(\)](#) to prompt the user to correct the error. [Prompt\(\)](#) is also used by the interactive resolve routine to prompt for options.

### Example

Consider the following user interaction with **p4 resolve**:

```
> p4 resolve file.c
c:\depot\file.c - merging //depot/file.c#2,#10
Diff chunks: 0 yours + 1 theirs + 0 both + 0 conflicting
Accept(a) Edit(e) Diff(d) Merge (m) Skip(s) Help(?) [at]: at
```

In the above example, the "msg" argument to [Prompt\(\)](#) is the "Accept...[at\]:" string. The response, "at", is placed into the "rsp" `StrBuf`, which is sent to the server and processed as "accept theirs".

To alter the behavior of [Prompt\(\)](#), create a subclass of `ClientUser` and provide an alternate implementation of [Prompt\(\)](#).

For example, suppose that you are writing a GUI application and want each option in the interactive resolve to appear in a dialog box. A function called `MyDialog()` to create a dialog box containing the text of its argument and a text field, and return a character array with the user's response, would look like this:

```
void MyClientUser::Prompt( const StrPtr &msg, StrBuf &buf, \
                          int noEcho, Error *e )
{
    buf.Set( MyDialog( msg.Text() ) );
}
```

## ClientUser::RunCmd( const char \*, const char \*, [...], Error \*)

Call an external program.

Virtual?	No	
Class	<a href="#">ClientUser</a> (static)	
Arguments	const char *command	the executable to be called
	const char *arg1	the first argument
	const char *arg2	the second argument
	const char *arg3	the third argument
	const char *arg4	the fourth argument
	const char *pager	a pager, if any
	Error *e	an Error object to hold system errors
Returns	void	

### Notes

[RunCmd\(\)](#) is called when the client needs to call an external program, such as a merge or diff utility. [RunCmd\(\)](#) stores any resulting errors in the specified Error object.

### Example

If you select "d" for "Diff" during an interactive resolve, and both **P4DIFF** and **P4PAGER** are set in your environment, [RunCmd\(\)](#) is called with the following arguments:

Argument	Value
command	<b>P4DIFF</b>
arg1	local file name
arg2	temp file name (depot file)
arg3	null
arg4	null
pager	<b>P4PAGER</b>

The **P4DIFF** program is called with the two file names as arguments, and the output is piped through the **P4PAGER** program.



See the examples for [Diff\(\)](#) and [Merge\(\)](#) for code illustrating the use of [RunCmd\(\)](#).

## Error methods

---

### Error::Clear()

Remove any error messages from an **Error** object.

Virtual?	No
Class	<a href="#">Error</a>
Arguments	None
Returns	void

### Notes

[Clear\(\)](#) can be used if you need to clear an **Error** after having handled it in a way that does not automatically clear it.

### Example

The following code attempts to establish a connection to a nonexistent server, displays the error's severity, clears the error, and shows that the error has been cleared:

```
ClientApi client;
Error e;

client.SetPort( "bogus:12345" );
client.Init( &e );

printf( "Error severity after Init() is is %d.\n", e.GetSeverity() );
e.Clear();
printf( "Error severity after Clear() is %d.\n", e.GetSeverity() );
```

Executing the preceding code produces the following output:

```
Error severity after Init() is 4.
Error severity after Clear() is 0.
```

## Error::Dump( const char \* )

Display an Error struct for debugging.

Virtual?	No
Class	<a href="#">Error</a>
Arguments	const char * trace    a string to appear next to the debugging output
Returns	void

### Notes

[Dump\(\)](#) can be used to determine the exact nature of an **Error** that is being handled. Its primary use is in debugging, as the nature of the output is more geared towards informing the developer than helping an end user.

### Example

The following code attempts to establish a connection to a nonexistent server, and dumps the resulting error:

```
ClientApi client;
Error e;

client.SetPort( "bogus:12345" );
client.Init( &e );

e.Dump( "example" );
```

Executing the preceding code produces the following output:

```
Error example 0012FF5C
Severity 4 (error)
Generic 38
Count 3
  0: 1093012493 (sub 13 sys 3 gen 38 args 1 sev 4 code 3085)
  0: %host%: host unknown.
  1: 1093012492 (sub 12 sys 3 gen 38 args 1 sev 4 code 3084)
  1: TCP connect to %host% failed.
  2: 1076240385 (sub 1 sys 8 gen 38 args 0 sev 4 code 8193)
  2: Connect to server failed; check $P4PORT.
  host = bogus
  host = bogus:12345
```

## Error::Fmt( StrBuf\* )

Format the text of an error into a `StrBuf`.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Error</a>	
<b>Arguments</b>	<code>StrBuf *buf</code>	a pointer to the <code>StrBuf</code> to contain the formatted error
<b>Returns</b>	<code>void</code>	

### Notes

The result of [Fmt\(\)](#) is suitable for displaying to an end user; this formatted text is what the command line client displays when an error occurs.

If an error has no severity (`E_EMPTY`), [Fmt\(\)](#) returns with no change to the `StrBuf`.

If the error has severity of info (`E_INFO`), the `StrBuf` is formatted.

If the error has any higher severity, the `StrBuf` argument passed to [Fmt\(\)](#) is cleared and then replaced with the formatted error.

### Example

The following example code displays an error's text:

```

if ( e.Test() )
{
    StrBuf msg;
    e.Fmt( &msg );
    printf( "ERROR:\n%s", msg.Text() );
}

```

## Error::Fmt( StrBuf \*, int )

Format the text of an error into a `StrBuf`, after applying formatting.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Error</a>	
<b>Arguments</b>	<code>StrBuf *buf</code>	a pointer to the <code>StrBuf</code> to contain the formatted error
	<code>int opts</code>	formatting options
<b>Returns</b>	<code>void</code>	

### Notes

The result of `Fmt()` is suitable for displaying to an end user; this formatted text is what the command line client displays when an error occurs.

If an error has no severity (`E_EMPTY`), `Fmt()` returns with no change to the `StrBuf`.

If the error has severity of info (`E_INFO`), the `StrBuf` is formatted.

If the error has any higher severity, the `StrBuf` argument passed to `Fmt()` is cleared and then replaced with the formatted error.

The `opts` argument is a flag or combination of flags defined by the `ErrorFmtOpts` enum. The default is `EF_NEWLINE`, which puts a newline at the end of the buffer.

Formatting options are as follows:

Argument	Value	Meaning
<code>EF_PLAIN</code>	<code>0x00</code>	perform no additional formatting.
<code>EF_INDENT</code>	<code>0x01</code>	indent each line with a tab ( <code>\t</code> )
<code>EF_NEWLINE</code>	<code>0x02</code>	default - terminate buffer with a newline ( <code>\n</code> )
<code>EF_NOXLATE</code>	<code>0x04</code>	ignore <b>P4LANGUAGE</b> setting

### Example

The following example code displays an error's text, indented with a tab.

```
if ( e.Test() )
{
    StrBuf msg;
    e.Fmt( &msg, EF_INDENT );
    printf( "ERROR:\n%s", msg.Text() );
}
```

## Error::GetGeneric()

Returns generic error code of the most severe error.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Error</a>	
<b>Arguments</b>	None	
<b>Returns</b>	int	the "generic" code of the most severe error

### Notes

For more sophisticated handling, use a "switch" statement based on the error number to handle different errors in different ways.

The generic error codes are not documented at this time.

### Example

The following example attempts to establish a connection to a nonexistent server, and displays the resulting generic error code.

```
ClientApi client;
Error e;

client.SetPort( "bogus:12345" );
client.Init( &e );

if ( e.Test() ) printf( "Init() failed, error code %d.\n", e.GetGeneric() );
```

Executing the preceding code produces the following output:

```
Init() failed, error code 38.
```

## Error::GetSeverity()

Returns severity of the most severe error.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Error</a>	
<b>Arguments</b>	None	
<b>Returns</b>	int	the severity of the most severe error

### Notes

The severity can take the following values:

Severity	Meaning
E_EMPTY (0)	no error
E_INFO (1)	information, not necessarily an error
E_WARN (2)	a minor error occurred
E_FAILED (3)	the command was used incorrectly
E_FATAL (4)	fatal error, the command can't be processed

### Example

The following code attempts to establish a connection to a server, and beeps if the severity is a warning or worse:

```
ClientApi client;
Error e;

client.SetPort( "magic:1666" );
client.Init( &e );

if ( e.GetSeverity() > E_INFO ) printf( "Uh-oh!%c\n", 13 );
```



## Error::IsFatal()

Tests whether there has been a fatal error.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">Error</a>
<b>Arguments</b>	None
<b>Returns</b>	int nonzero if error is fatal

### Notes

This function returns nonzero if [GetSeverity\(\)](#) == E\_FATAL.

### Example

The following code attempts to establish a connection to a server, and beeps if the severity is fatal:

```
ClientApi client;
Error e;

client.SetPort( "magic:1666" );
client.Init( &e );

if ( e.IsFatal() ) printf( "Fatal error!%c\n", 13 );
```

## Error::IsWarning()

Tests whether the error is a warning.

Virtual?	No
Class	<a href="#">Error</a>
Arguments	None
Returns	int nonzero if the most severe error is a warning

### Notes

This function returns nonzero if [GetSeverity\(\)](#) == E\_WARN.

### Example

The following code attempts to establish a connection to a server, and beeps if the severity is a warning:

```
ClientApi client;
Error e;

client.SetPort( "magic:1666" );
client.Init( &e );

if ( e.IsWarning() ) printf( "Warning!%c\n", 13 );
```

## **Error::Net( const char \*, const char \* )**

Add a network-related error to an `Error`.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Error</a>	
<b>Arguments</b>	<code>const char *op</code>	the network operation that was attempted
	<code>const char *arg</code>	relevant information about that operation
<b>Returns</b>	<code>void</code>	

### **Notes**

To use an `Error` object to track network-related errors, use [Net\(\)](#). Note that network communication with the Perforce server and related errors are already handled by lower levels of the client API.

### **Example**

The following example adds an error message, related to a failure to bind to a network interface, to an `Error` object.

```
e.Net( "bind", service.Text() );
```

## Error::operator << ( int )

Add data to the text of an error message.

<b>Virtual?</b>	No	
	<b>Class</b>	<a href="#">Error</a>
<b>Arguments</b>	int arg	text to be added to this <b>Error</b>
<b>Returns</b>	<b>Error &amp;</b>	a reference to the modified <b>Error</b>

### Notes

The “<<” operator can be used to add text to an error as if the error is an output stream. This operator is typically used in the implementation of other **Error** methods.

Note that an **Error** consists of more than its text, it’s more useful to use [Set\(\)](#) to establish a base **Error** and then add text into that, rather than merely adding text to an empty **Error** object.

### Example

The following example creates an **Error** using [Set\(\)](#) and the << operator.

```
e.Set( E_WARN, "Warning, number " ) << myErrNum;
```

**Error::operator << ( char \* )**

Add data to the text of an error message.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Error</a>	
<b>Arguments</b>	char *arg	text to be added to this <b>Error</b>
<b>Returns</b>	<b>Error &amp;</b>	a reference to the modified <b>Error</b>

**Notes**

The “<<” operator can be used to add text to an error as if the error is an output stream. This operator is typically used in the implementation of other **Error** methods.

Note that an **Error** consists of more than its text, it’s more useful to use [Set\(\)](#) to establish a base **Error** and then add text into that, rather than merely adding text to an empty **Error** object.

**Example**

The following example creates an **Error** using [Set\(\)](#) and the << operator.

```
e.Set( E_WARN, "Warning! " ) << "Something bad happened";
```

## **Error::operator << ( const StrPtr & )**

Add data to the text of an error message.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Error</a>	
<b>Arguments</b>	<code>const StrPtr &amp;arg</code>	text to be added to this <b>Error</b>
<b>Returns</b>	<code>Error &amp;</code>	a reference to the modified <b>Error</b>

### **Notes**

See [Error::operator << \(int\)](#) for details.

## **Error::operator = ( Error & )**

Copy an error.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Error</a>	
<b>Arguments</b>	<b>Error &amp; source</b>	the <b>Error</b> to be copied
<b>Returns</b>	void	

### **Notes**

The “=” operator copies one **Error** into another.

### **Example**

The following example sets **Error e1** to equal **e2**.

```
Error e1, e2;  
e1 = e2;
```

## Error::Set( enum ErrorSeverity, const char \* )

Add an error message to an Error.

Virtual?	No
Class	<a href="#">Error</a>
Arguments	enum ErrorSeverity s const char *fmt
Returns	void

### Notes

An Error can hold multiple error messages; [Set\(\)](#) adds the error message to the Error, rather than replacing the Error's previous contents.

An ErrorSeverity is an int from 0-4 as described in the documentation on [GetSeverity\(\)](#).

### Example

The following example adds a fatal error to an Error object.

```
Error e;  
e.Set( E_FATAL, "Fatal error!");
```



## Error::Set( ErrorId & )

Add an error message to an `Error`.

Virtual?	No	
Class	<a href="#">Error</a>	
Arguments	<code>ErrorId&amp; id</code>	the severity and text of the error message
Returns	<code>void</code>	

### Notes

See [Error::Set\( enum ErrSeverity, const char \\* \)](#) for details.

An `ErrorId` is a struct containing an `int (s)` and a `const char * (fmt)`.

## **Error::Sys( const char \*, const char \* )**

Add a system error to an `Error`.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Error</a>	
<b>Arguments</b>	<code>const char *op</code>	the system call that was attempted
	<code>const char *arg</code>	relevant information about that call
<b>Returns</b>	<code>void</code>	

### **Notes**

To use an `Error` object to track errors generated by system calls such as file operations, use [Sys\(\)](#).

### **Example**

The following example adds an error message, related to a failure to rename a file, to an `Error` object.

```
e.Sys( "rename", targetFile->Name() );
```

## Error::Test()

Test whether an `Error` is non-empty.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Error</a>	
<b>Arguments</b>	None	
<b>Returns</b>	int	nonzero if the error is non-empty

### Notes

`Test()` returns nonzero if `GetSeverity() != E_EMPTY`.

### Example

The following code attempts to establish a connection to a server, and beeps if an error occurs:

```
ClientApi client;
Error e;

client.SetPort( "magic:1666" );
client.Init( &e );

if ( e.Test() ) printf( "An error has occurred.%c\n", 13 );
```

## ErrorLog methods

### ErrorLog::Abort()

Abort with an error status if an error is detected.

Virtual?	No
Class	<a href="#">ErrorLog</a>
Arguments	None
Returns	void

### Notes

If the error is empty (severity is `E_EMPTY`), [Abort\(\)](#) returns. Otherwise [Abort\(\)](#) causes the program to exit with a status of -1.

### Example

[Abort\(\)](#) is typically called after [Init\(\)](#) or [Run\(\)](#) to abort the program with a non-zero status if there has been a connection problem. The code in `p4api.cc` is one example:

```
ClientApi client;
Error e;

client.Init( &e );
ErrorLog::Abort();
```

If any errors are generated during `ClientApi::Init()`, the `Error` object is non-empty, and [Abort\(\)](#) reports the connection error before terminating the program.

## ErrorLog::Report()

Print the text of an error to `stderr`.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ErrorLog</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>void</code>

### Notes

[Report\(\)](#) functions similarly to [Error::Fmt\(\)](#), but displays the text on `stderr` rather than copying it into a `StrBuf`.

### Example

The following example displays the contents of an error.

```
ClientApi client;
Error e;

client.Init( &e );
ErrorLog::Report();
```

## ErrorLog::SetLog( const char \* )

Redirects this Error's [Report\(\)](#) output to a file.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ErrorLog</a>	
<b>Arguments</b>	const char *file	the file to serve as an error log
<b>Returns</b>	void	

### Notes

After [SetLog\(\)](#) is called on a given **Error** object, [Report\(\)](#) directs its output to the specified file rather than `stderr`. This setting applies only to the specified **Error** object.

### Example

The following example redirects an **Error**'s output to a log file, and then writes the **Error**'s text to that log file.

```
ClientApi client;
Error e;

ErrorLog::SetLog( "C:\Perforce\errlog" );
client.Init( &e );
ErrorLog::Report();
```

## ErrorLog::SetSyslog()

Redirects this Error's [Report\(\)](#) output to **syslog** on UNIX only.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ErrorLog</a>
<b>Arguments</b>	None
<b>Returns</b>	void

### Notes

This method is only valid on UNIX. After it is called, the output of [Report\(\)](#) is redirected to **syslog**, similar to [SetLog\(\)](#).

### Example

The following example redirects an Error's output to **syslog**, and then outputs the Error's text to **syslog**.

```
ClientApi client;
Error e;

ErrorLog::SetSyslog();
client.Init( &e );
ErrorLog::Report();
```

## ErrorLog::SetTag( const char \* )

Changes the standard tag used by this Error's [Report\(\)](#) method.

Virtual?	No
Class	<a href="#">ErrorLog</a>
Arguments	const char *tag      the text of the new tag
Returns	void

### Notes

The default tag is "Error". [SetTag\(\)](#) sets the new tag for the specified Error object only.

### Example

The following example resets the tag on an Error to be "NewError".

```
ClientApi client;
Error e;

client.Init( &e );
ErrorLog::SetTag( "NewError" );
```



## ErrorLog::UnsetSyslog()

Stop writing errors to **syslog**.

Virtual?	No
Class	<a href="#">ErrorLog</a>
Arguments	None
Returns	void

### Notes

[UnsetSyslog\(\)](#) reverses the effect of [SetSyslog\(\)](#) by resetting the **Error** object to output to **stderr**.

### Example

The following example prints an error message to **syslog** and then resets the **Error** back to using **stderr** for output.

```
ClientApi client;
Error e;

client.Init( &e );
ErrorLog::SetSyslog();
ErrorLog::Report();
ErrorLog::UnsetSyslog();
```

## FileSys methods

### FileSys::Chmod( FilePerm, Error \* )

Modify the file mode bits of the file specified by the `path` protected `FileSys` member.

Virtual?	Yes	
Class	<a href="#">FileSys</a>	
Arguments	FilePerm perms	permissions to change the file, either FPM_RO (read only) or FPM_RW (read/write)
	Error *error	returned error status
Returns	void	

### Notes

This method is called to make a client file writable (FPM\_RW) when it is opened for `edit`, or to change it to read-only (FPM\_RO) after a `submit`.

A `FilePerm` is an `enum` taking one of the following values:

Argument	Value	Meaning
FPM_RO	0x00	leave file read-only.
FPM_RW	0x01	allow read and write operations

### Example

To use [Chmod\(\)](#) to create a configuration file and set its permissions to read-only:

```
FileSys *f = FileSys::Create( FST_ATEXT );
Error e;

f->Set( "c:\\configfile.txt" );
f->Chmod( FPM_RO, &e );
```

To reimplement [Chmod\(\)](#) under UNIX:

```
void FileSysDemo::Chmod( FilePerm perms, Error *e )
{
    int bits = IsExec() ? PERM_0777 : PERM_0666;

    if ( perms == FPM_RO )
        bits &= ~PERM_0222;

    if ( chmod( Name(), bits & ~myumask ) < 0 )
        e->Sys( "chmod", Name() );

    if ( DEBUG )
        printf( "Debug (Chmod): %s\n", Name() );
}
```

## FileSys::Close( Error \* )

Close the file specified by the `path` protected `FileSys` member and release any OS resources associated with the open file.

Virtual?	Yes	
Class	<a href="#">FileSys</a>	
Arguments	Error *error	returned error status
Returns	void	

### Notes

The default implementation of [Close\(\)](#) is called every time a file that is currently [Open\(\)](#) is no longer required. Typically, the handle that was returned for the [Open\(\)](#) call is used to free up the resource.

Your implementation must correctly report any system errors that may occur during the close.

### Example

To use [Close\(\)](#) to close an open file:

```
FileSys *f = FileSys::Create( FST_ATEXT );
Error e;

f->Set( "c:\\configfile.txt" );
f->Open( FOM_WRITE, &e );
f->Close( &e );
```

To reimplement [Close\(\)](#) to report errors using [Error::Sys\(\)](#) and provide debugging output:

```
void FileSysDemo::Close( Error *e )
{
    if ( close( fd ) == -1 )
        e->Sys( "close", Name() );

    if ( DEBUG )
        printf( "Debug (Close): %s\n", Name() );
}
```

## FileSys::Create( FileSystemType )

Create a new FileSys object.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">FileSys</a>	
<b>Arguments</b>	FileSystemType type	file type
<b>Returns</b>	FileSys *	a pointer to the new FileSys.

### Notes

A `FileSystemType` is an `enum` taking one of the values defined in `filesystem.h`. The most commonly used `FileSystemTypes` are as follows:

Argument	Value	Meaning
FST_TEXT	0x0001	file is text
FST_BINARY	0x0002	file is binary
FST_ATEXT	0x0011	file is text, open only for append

### Example

To use [Create\(\)](#) to create a `FileSys` object for a log file (text file, append-only):

```
FileSys *f = FileSys::Create( FST_ATEXT );
```

## FileSys::Open( FileOpenMode, Error \* )

Open the file name specified by the `path` protected `FileSys` member for reading or writing as specified by the argument `FileOpenMode`.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">FileSys</a>	
<b>Arguments</b>	<code>FileOpenMode mode</code>	Mode to open the file, either <code>FOM_READ</code> (open for read) or <code>FOM_WRITE</code> (open for write)
	<code>Error *error</code>	returned error status
<b>Returns</b>	<code>void</code>	

### Notes

The default implementation of [Open\(\)](#) is called every time there is a need to create or access a file on the client workspace.

Operating systems typically return a handle to the opened file, which is then used to allow future read/write calls to access the file.

Your implementation must correctly report any system errors that may occur during the open.

### Example

To use [open\(\)](#) to open a log file for writing:

```
FileSys *f = FileSys::Create( FST_ATEXT );
Error e;
StrBuf m;
m.Append( "example: text to append to a log file\r\n" );

f->Set( "C:\\logfile.txt" );
f->Open( FOM_WRITE, &e );
f->Write( m.Text(), m.Length(), &e );
f->Close( &e );
```

To reimplement [Open\(\)](#) to report errors with [Error::Sys\(\)](#), provide debugging output, and use the `FileSysDemo` member `"fd"` to hold the file handle returned from the `open()` system call:

```
void FileSysDemo::Open( FileOpenMode mode, Error *e )
{
    this->mode = mode;

    int bits = ( mode == FOM_READ ) ? O_RDONLY
                                     : O_WRONLY|O_CREAT|O_APPEND;

    if ( ( fd = open( Name(), bits, PERM_0666 ) ) < 0 )
    {
        e->Sys( mode == FOM_READ ? "open for read" : "open for write",
              Name() );
    }

    if ( DEBUG )
    {
        printf( "Debug (Open): '%s' opened for '%s'\n", Name(),
              mode == FOM_READ ? "read" : "write" );
    }
}
```

## FileSys::Read( const char \*, int, Error \* )

Attempt to read `len` bytes of data from the object referenced by the file handle (returned by the [Open\(\)](#) method) to the buffer pointed to by `buf`. Upon successful completion, [Read\(\)](#) returns the number of bytes actually read and placed in the buffer.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">FileSys</a>	
<b>Arguments</b>	<code>const char *buf</code>	pointer to buffer into which to read data
	<code>int len</code>	length of data to read
	<code>Error *error</code>	returned error status
<b>Returns</b>	<code>int</code>	number of bytes actually read

### Notes

The default implementation of [Read\(\)](#) is called every time there is a need to read data from the file referenced by the [Open\(\)](#) call.

Your implementation must correctly report any system errors that may occur during I/O.

### Example

To use [Read\(\)](#) to read a line from a log file:

```
char line[80];
m.Set( msg );
FileSys *f = FileSys::Create( FST_ATEXT );
Error e;

f->Set( "C:\\logfile.txt" );
f->Open( FOM_READ, &e );
f->Read( line, 80, &e );
f->Close( &e );
```

To reimplement [Read\(\)](#) to report errors with [Error::Sys\(\)](#), provide debugging output, and use the `FileSysDemo` member `"fd"` to hold the file handle returned from the `read()` system call:



```
int FileSysDemo::Read( char *buf, int len, Error *e )
{
    int bytes;

    if ( ( bytes = read( fd, buf, len ) ) < 0 )
        e->Sys( "read", Name() );

    if ( DEBUG )
    {
        printf( "debug (Read): %d bytes\n", bytes );
    }

    return( bytes );
}
```

## FileSys::Rename( FileSys \*, Error \* )

Rename the file specified by the `path` protected `FileSys` member to the file specified by the `target` `FileSys` object.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">FileSys</a>	
<b>Arguments</b>	<code>FileSys *target</code>	name of target for rename
	<code>Error *error</code>	returned error status
<b>Returns</b>	<code>void</code>	

### Notes

On some operating systems, an `unlink` might be required before calling [Rename\(\)](#).

Your implementation must correctly report any system errors that may occur during the rename.

### Example

To use [Rename\(\)](#) to rename `/usr/logs/log2` to `/usr/logs/log1`:

```
FileSys *f1 = FileSys::Create( FST_TEXT );
FileSys *f2 = FileSys::Create( FST_TEXT );
Error e;

f1->Set( "/usr/logs/log1" );
f2->Set( "/usr/logs/log2" );

f1->Rename( f2, &e );
```

To reimplement [Rename\(\)](#) to report errors with [Error::Sys\(\)](#) and provide debugging output:

```
void FileSysDemo::Rename( FileSys *target, Error *e )
{
    if ( rename( Name(), target->Name() ) < 0 )
        e->Sys( "rename", Name() );

    if ( DEBUG )
        printf( "Debug (Rename): %s to %s\n", Name(), target->Name() );
}
```

## FileSys::Set( const StrPtr \* )

Initializes the protected `StrBuf` variable `path` to the supplied filename argument; this `path` is used by other `FileSys` member functions when reading and writing to a physical file location.

Virtual?	Yes
Class	<a href="#">FileSys</a>
Arguments	<code>const StrPtr *name</code> filename for this <code>FileSys</code> object
Returns	<code>void</code>

### Notes

After creating a `FileSys` object, call [Set\(\)](#) to supply it with a `path`.

### Example

To use [Set\(\)](#) to set a filename:

```
FileSys *f = FileSys::Create( FST_BINARY );
f->Set( "/tmp/file.bin" );
```

To reimplement [Set\(\)](#) to provide debugging output:

```
void FileSysDemo::Set( const StrPtr &name )
{
    // Set must initialize the protected variable "path"
    // with the filename argument "name".

    path.Set( name );

    if ( DEBUG )
        printf( "debug (Set): %s\n", path.Text() );
}
```

## FileSys::Stat()

Obtain information about the file specified by the `path` protected `FileSys` member.

<b>Virtual?</b>	Yes
<b>Class</b>	<a href="#">FileSys</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>int</code> 0 for failure, or status bits as defined below

The status bits have the following meanings:

Status	Meaning
0	failure
FSF_EXISTS (0x01)	file exists
FSF_WRITEABLE (0x02)	file is user-writable
FSF_DIRECTORY (0x04)	file is a directory
FSF_SYMLINK (0x08)	file is symlink
FSF_SPECIAL (0x10)	file is a special file (in the UNIX sense)
FSF_EXECUTABLE (0x20)	file is executable
FSF_EMPTY (0x40)	file is empty
FSF_HIDDEN (0x80)	file is invisible (hidden)

### Notes

The default implementation of [Stat\(\)](#) is called to obtain file status every time a file is opened for read.

### Example

To use [Stat\(\)](#) to verify the existence of `/usr/bin/p4`:

```
FileSys *f = FileSys::Create( FST_BINARY );
f->Set( "/usr/bin/p4" );
int state = f->Stat();

if ( state & FSF_EXISTS )
    printf( "File found\n" );
```

To reimplement [Stat\(\)](#) to provide debugging output:

```
int FileSysDemo::Stat()
{
    int flags = 0;
    struct stat st;

    if ( DEBUG )
        printf( "Debug (Stat): %s\n", Name() );

    if ( stat( Name(), &st ) < 0 )
        return( flags );

    // Set internal flags

    flags |= FSF_EXISTS;

    if ( st.st_mode & S_IWUSR ) flags |= FSF_WRITEABLE;
    if ( st.st_mode & S_IXUSR ) flags |= FSF_EXECUTABLE;
    if ( S_ISDIR( st.st_mode ) ) flags |= FSF_DIRECTORY;
    if ( !S_ISREG( st.st_mode ) ) flags |= FSF_SPECIAL;
    if ( !st.st_size ) flags |= FSF_EMPTY;
    return flags;
}
```

## FileSys::StatModTime()

Return the last modified time of the file specified by the `path` protected `FileSys` member.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">FileSys</a>	
<b>Arguments</b>	None	
<b>Returns</b>	<code>int</code>	0 for failure, or last modified time in seconds since 00:00:00, January 1, 1970, GMT.

### Notes

The default implementation of [StatModTime\(\)](#) is called every time a client file is submitted or synced.

### Example

To use [StatModTime\(\)](#) to obtain the modification time on a log file:

```
FileSys *f = FileSys::Create( FST_ATEXT );
f->Set( "/usr/logs/logfile.txt" );
int time = f->StatModTime();

if ( time )
    printf( "%d", time );
```

To reimplement [StatModTime\(\)](#) to provide debugging output:

```
int FileSysDemo::StatModTime()
{
    struct stat st;

    if ( stat( Name(), &st ) < 0 )
        return( 0 );

    if ( DEBUG )
        printf( "Debug (StatModTime): %s\n", Name() );

    return (int)( st.st_mtime );
}
```

## FileSys::Truncate()

Truncate the file specified by the `path` protected `FileSys` member to zero length.

<b>Virtual?</b>	Yes
<b>Class</b>	<a href="#">FileSys</a>
<b>Arguments</b>	None
<b>Returns</b>	void

### Notes

The default implementation of [Truncate\(\)](#) is only called by the Perforce server.

## FileSys::Unlink( Error \* )

Remove the file specified by the `path` protected `FileSys` member from the filesystem.

Virtual?	Yes	
Class	<a href="#">FileSys</a>	
Arguments	Error *error	returned error status
Returns	void	

### Notes

The default implementation of [Unlink\(\)](#) is always called if the file created is temporary.

Your implementation must correctly report any system errors that may occur during removal.

### Example

To use [Unlink\(\)](#) to delete an old log file:

```
FileSys *f = FileSys::Create( FST_TEXT );
Error e;

f->Set( "/usr/logs/oldlog" );
f->Unlink( &e );
```

To reimplement [Unlink\(\)](#) to report errors with [Error::Sys\(\)](#) and provide debugging output:

```
void FileSysDemo::Unlink( Error *e )
{
    if ( unlink( Name() ) < 0 )
        e->Sys( "unlink", Name() );

    if ( DEBUG )
        printf( "Debug (Unlink): %s\n", Name() );
}
```



## FileSys::Write( const char \*, int, Error \*)

Attempt to write “len” bytes of data to the object referenced by the file handle (returned by the [Open\(\)](#) method) from the buffer pointed to by “buf”.

<b>Virtual?</b>	Yes	
<b>Class</b>	<a href="#">FileSys</a>	
<b>Arguments</b>	const char *buf	pointer to buffer containing data to be written
	int len	length of data to write
	Error *error	returned error status
<b>Returns</b>	void	

### Notes

The default implementation of [Write\(\)](#) is called every time there is a need to write data to the file created by the [Open\(\)](#) call.

Your implementation must correctly report any system errors that may occur during I/O.

### Example

To use [Write\(\)](#) to write an error to a log file:

```
StrBuf m;
m.Set( "Unknown user\r\n" );
FileSys *f = FileSys::Create( FST_ATEXT );
Error e;

f->Set( "C:\\logfile.txt" );
f->Open( FOM_WRITE, &e );
f->Write( m.Text(), m.Length(), &e );
f->Close( &e );
```

To reimplement [Write\(\)](#) to report errors with [Error::Sys\(\)](#) and provide debugging output:

```
void FileSysDemo::Write( const char *buf, int len, Error *e )
{
    int bytes;

    if ( ( bytes = write( fd, buf, len ) ) < 0 )
        e->Sys( "write", Name() );

    if ( DEBUG )
        printf( "debug (Write): %d bytes\n", bytes );
}
```

## Ignore methods

### Ignore::Reject( const StrPtr &, const StrPtr & )

Tests whether the provided path will be rejected when it is opened for add because it matches an entry in the provided ignore file.

Virtual?	No	
Class	<a href="#">Ignore</a>	
Arguments	const StrPtr &path	the path to check
	const StrPtr &ignoreFile	the full path to the ignore file
Returns	int	nonzero if path is ignored

### Notes

Calling [Reject\(\)](#) provides a preview of what will happen when files are opened for add.

If the ignore file does not exist, or is not readable, no files are rejected.

### Example

The following example demonstrates the usage of [Reject\(\)](#).

```
# include "clientapi.h"
# include "ignore.h"

int main()
{
    ClientApi client;
    StrBuf clientPath;

    client.SetIgnoreFile( ".p4ignore" );
    clientPath = "ignore.txt";
    if ( client->GetIgnore()->Reject( *clientPath,
                                     client->GetIgnoreFile() ) )
    {
        printf( "%s is to be ignored.\n", clientPath.Text() );
    }
}
```

## Ignore::RejectCheck( const StrPtr & )

Tests whether the provided path will be rejected when it is opened for add because it matches an ignore file entry.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Ignore</a>	
<b>Arguments</b>	const StrPtr &path	the path to check
<b>Returns</b>	int	nonzero if path is ignored

### Notes

Calling [RejectCheck\(\)](#) provides a preview of what will happen the file is opened for add.

Use [RejectCheck\(\)](#) when you have to test multiple paths that may be rejected. First call [Reject\(\)](#) to parse the ignore file, and then call [RejectCheck\(\)](#) for each additional path that needs to be checked.

### Example

The following example demonstrates the usage of [RejectCheck\(\)](#).

```
# include "clientapi.h"
# include "ignore.h"

int main()
{
    ClientApi client;
    StrBuf clientPath;

    client.SetIgnoreFile( ".p4ignore" );
    clientPath = "ignore.txt";
    if ( client->GetIgnore()->Reject( *clientPath,
                                     client->GetIgnoreFile() ) )
    {
        printf( "%s is to be ignored.\n", clientPath.Text() );
    }

    clientPath = "ignore2.txt";
    if ( client->GetIgnore()->Reject( *clientPath,
                                     client->GetIgnoreFile() ) )
    {
        printf( "%s is to be ignored.\n", clientPath.Text() );
    }
}
```

## KeepAlive methods

### KeepAlive::IsAlive()

The only method of the [KeepAlive](#) class, [IsAlive\(\)](#) is used in applications to request that the current command be terminated by disconnecting.

Virtual?	Yes	
Class	<a href="#">KeepAlive</a>	
Arguments	None	
Returns	int	0 to terminate connection, 1 to continue processing

### Notes

Use [ClientApi::SetBreak\(\)](#) to establish a callback to be called every 0.5 seconds during command execution.

### See also

[ClientApi::SetBreak\(\)](#)

### Example

The following example implements a custom [IsAlive\(\)](#) that can be called three times before returning 0 and terminating the connection. If the call to run the **changes** command takes less than 1.5 seconds to complete on the server side, the program outputs the list of changes. If the call to run the **changes** command takes more than 1.5 seconds, the connection is interrupted.

```
#include <clientapi.h>

// subclass KeepAlive to implement a customized IsAlive function.
class MyKeepAlive : public KeepAlive
{
    public:
    int IsAlive();
};

// Set up the interrupt callback. After being called 3 times,
// interrupt 3 times, interrupt the current server operation.
int MyKeepAlive::IsAlive()
{
    static int counter = 0;
    if ( ++counter > 3 )
    {
        counter = 0;
        return( 0 );
    }
    return( 1 );
}

// Now test the callback
ClientUser ui;
ClientApi client;
MyKeepAlive cb;
Error e;

client.Init( &e );
client.SetBreak( &cb ); // SetBreak must happen after the Init
client.Run( "changes", &ui );
client.Final( &e );
```

## MapApi methods

---

### MapApi::Clear()

Empties a mapping.

Virtual?	No
Class	<a href="#">MapApi</a>
Arguments	None
Returns	void

### Notes

After this method has been called on a **MapApi** object, the object is indistinguishable from a freshly-constructed object.

## MapApi::Count()

Returns the number of entries currently in the mapping.

Virtual?	No	
Class	<a href="#">MapApi</a>	
Arguments	None	
Returns	int	The number of entries currently in the mapping

### Notes

The number returned by [Count\(\)](#) may be different from the number of times that [Insert\(\)](#) has been called. This is because `MapApi` automatically disambiguates itself, adding new exclusions to eliminate ambiguity between partially overlapping entries and removing entries that are redundant.

### Example

The following example demonstrates [Count\(\)](#), [GetType\(\)](#), [GetLeft\(\)](#), and [GetRight\(\)](#) being used to iterate over a `MapApi` that contains four entries after two calls to [Insert\(\)](#).

This code produces the following output:

```
//depot/... //client/...
-//depot/d2/... //client/d2/...
-//depot/d1/... //client/d1/...
//depot/d1/... //client/d2/...
```

```
MapApi clientmap;

clientmap.Insert( StrRef( "//depot/..." ), StrRef( "//client/..." ) );
clientmap.Insert( StrRef( "//depot/d1/..." ), StrRef( "//client/d2/..." ) );

char c = ' ';
for ( int i = 0; i < clientmap.Count(); i++ )
{
    switch( clientmap.GetType( i ) )
    {
        case MapInclude:
            c = ' '; break;
        case MapExclude:
            c = '-'; break;
        case MapOverlay:
            c = '+'; break;
    }

    printf( "%c%s %s\n", c,
            clientmap.GetLeft( i )->Text(),
            clientmap.GetRight( i )->Text() );
}
```



## MapApi::GetLeft( int )

Returns the left side of the specified view entry.

Virtual?	No	
Class	<a href="#">MapApi</a>	
Arguments	<code>int i</code>	the index of the desired entry
Returns	<code>const StrPtr *</code>	a string representing the left side of the entry

### Notes

The index should be between 0 and one less than the number of mapping entries.

### See also

[MapApi::Count\(\)](#)

### Example

See the example for [MapApi::Count\(\)](#).

## MapApi::GetRight( int )

Returns the right side of the specified view entry.

Virtual?	No	
Class	<a href="#">MapApi</a>	
Arguments	<code>int i</code>	the index of the desired entry
Returns	<code>const StrPtr *</code>	a string representing the right side of the entry

### Notes

The index should be between 0 and one less than the number of mapping entries.

### See also

[MapApi::Count\(\)](#)

### Example

See the example for [MapApi::Count\(\)](#).

## MapApi::GetType( int )

Returns the type of the specified view entry.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">MapApi</a>	
<b>Arguments</b>	<code>int i</code>	the index of the desired entry
<b>Returns</b>	<code>MapType</code>	the entry type

### Notes

The entry type is one of `MapInclude`, `MapExclude`, and `MapOverlay`.

`MapExclude` entries negate earlier `MapInclude` and `MapOverlay` entries that map the same paths, and `MapOverlay` entries are not disambiguated if they overlap with earlier `MapInclude` entries.

In human-readable Perforce view specifications, `MapExclude` lines are indicated with a - character, and `MapOverlay` lines are indicated with a + character.

### See also

[MapApi::Count\(\)](#)

### Example

See the example for [MapApi::Count\(\)](#).

## MapApi::Insert( const StrPtr &, MapType )

Adds a new entry to the mapping.

Virtual?	No	
Class	<a href="#">MapApi</a>	Arguments
StrPtr & lr	the path to which the entry applies	
MapType t	the mapping type (by default, MapInclude)	Returns

### Notes

This [Insert\(\)](#) overload is a convenience function that adds an entry with identical left and right sides. It is meant to represent mappings whose sole purpose is to include and exclude files, such as protection tables and label views.

### Example

The following example demonstrates the construction and use of a protection table mapping.

```
MapApi protect;
protect.Insert( StrRef( "//..." ) );
protect.Insert( StrRef( "//private/..." ), MapExclude );

StrBuf to;
StrBuf file1( "//depot/file.txt" );
StrBuf file2( "//private/file.txt" );

printf( "%s - access %d\n", file1.Text(), protect.Translate( file1, to ) );

printf( "%s - access %d\n", file2.Text(), protect.Translate( file2, to ) );
```

This produces the following output:

```
//depot/file.txt - access 1
//private/file.txt - access 0
```

## MapApi::Insert( const StrPtr &, const StrPtr &, MapType )

Adds a new entry to the mapping.

Virtual?	No	
Class	<a href="#">MapApi</a>	
Arguments	StrPtr & l	the left side of the entry
	StrPtr & r	the right side of the entry
	MapType t	the mapping type (by default, <code>MapInclude</code> )
Returns	void	

### Notes

[Insert\(\)](#) adds one new entry to a mapping at the "bottom" (highest precedence) position in the map. The `MapType` parameter indicates whether the entry is a standard inclusion (the default), an exclusion, or an overlay mapping (only useful when modeling a client view).

### Example

The following example demonstrates the construction and use of a branch view mapping.

```
MapApi branch;
branch.Insert( StrRef( "//depot/main/..." ), StrRef( "//depot/rel1/..." ) );

StrBuf source( "//depot/main/file.c" );
StrBuf target;

branch.Translate( source, target );
printf( "%s -> %s\n", source.Text(), target.Text() );
```

This produces the following output:

```
//depot/main/file.c -> //depot/rel1/file.c
```

## MapApi::Join( MapApi \*, MapApi \* ) [static]

Joins two `MapApis` together to produce a combined mapping.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">MapApi</a>	
<b>Arguments</b>	<code>MapApi *left</code>	the first mapping
	<code>MapApi *right</code>	the second mapping
<b>Returns</b>	<code>MapApi *</code>	a new <code>MapApi</code> representing the joined maps

### Notes

This overload of [Join\(\)](#) links the right side of the first mapping to the left side of the second mapping, as if the two mappings were laid out left to right and glued together in the middle. The resulting `MapApi`'s left side corresponds to the first mapping's left side, and its right side corresponds to the second mapping's right side.

If the right side of the first mapping does not have anything in common with the left side of the second mapping, the resulting map is empty.

The other [Join\(\)](#) overload allows more control over which side of each mapping is joined to the other, and the direction of the resulting mapping.

This function allocates a new `MapApi` object on the heap; the caller is responsible for deleting it.

### Example

The following example demonstrates a join between a branch view and a client view.

```

MapApi branchmap;
branchmap.Insert( StrRef( "//depot/main/..." ), StrRef( "//depot/re1/..." ) );

MapApi clientmap;
clientmap.Insert( StrRef( "//depot/..." ), StrRef( "//client/depot/..." ) );

MapApi *branch_to_client = MapApi::Join( &branchmap, &clientmap );

StrBuf source( "//depot/main/file.c" );
StrBuf target;

branch_to_client->Translate( source, target );
printf( "%s -> %s\n", source.Text(), target.Text() );
delete branch_to_client;

```

This produces the following output:

```
//depot/main/file.c -> //client/depot/rel1/file.c
```

**MapApi::Join( MapApi \*, MapDir, MapApi \*, MapDir ) [static]**

Joins two `MapApis` together to produce a combined mapping.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">MapApi</a>	
<b>Arguments</b>	<code>MapApi *m1</code>	the first mapping
	<code>MapDir d1</code>	the orientation of the first mapping
	<code>MapApi *m2</code>	the second mapping
	<code>MapDir d2</code>	the orientation of the second mapping
<b>Returns</b>	<code>MapApi *</code>	a new <code>MapApi</code> representing the joined maps

**Notes**

This overload of [Join\(\)](#) works exactly like the simpler two-argument overload, but allows the caller to reverse either or both mappings before they are joined together. Specifying `MapLeftRight` as the direction for both mappings will produce the same result as the two-argument [Join\(\)](#).

If the two mappings do not have anything in common at the join point, the result is an empty mapping.

This function allocates a new `MapApi` object on the heap; the caller is responsible for deleting it.

**Example**

The following example demonstrates a join between a branch view and a client view, with both mappings reversed so that the client path is on the left side of the result and the branch source is on the right side.

```
MapApi branchmap;
branchmap.Insert( StrRef( "//depot/main/..." ), StrRef( "//depot/rel1/..." ) );

MapApi clientmap;
clientmap.Insert( StrRef( "//depot/..." ), StrRef( "//client/depot/..." ) );

MapApi *client_to_branch = MapApi::Join
    ( &clientmap, MapRightLeft, &branchmap, MapRightLeft );

StrBuf clientFile( "//client/depot/rel1/file.c" );
StrBuf branchFile;

client_to_branch->Translate( clientFile, branchFile );
printf( "%s -> %s\n", clientFile.Text(), branchFile.Text() );
delete client_to_branch;
```



Executing the preceding code produces the following output:

```
//client/depot/rel1/file.c -> //depot/main/file.c
```

## MapApi::Translate( const StrPtr &, StrBuf&, MapDir )

Translates a file path from one side of a mapping to the other.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">MapApi</a>	
<b>Arguments</b>	const StrPtr & from	the input path
	StrBuf & to	the output path
	MapDir d	the direction in which to translate (by default, MapLeftRight)
<b>Returns</b>	bool	whether or not the translation succeeded

### Notes

The [Translate\(\)](#) function is used to determine the effect of the mapping on any particular file. In the case of a two-sided mapping (such as a client view), it indicates where any given depot file maps in the client, or vice versa. In the case of a one-sided mapping (such as a protection table), it simply indicates whether a particular file is mapped at all.

If the specified `MapDir` is `MapLeftRight`, the input path is translated from the left side of the mapping to the right side of the mapping. If the `MapDir` is `MapRightLeft`, the mapping is effectively inverted, so that the input path is translated from the right side to the left.

If the input path does not match anything in the left side of the mapping (or the right side in the `MapRightLeft` case), the translation fails just as if the input path had been excluded from the mapping.

[Translate\(\)](#) is designed to map single files. To model the effect of passing a broader path through a mapping, create a new one-sided mapping that represents that path and [Join\(\)](#) it with the other mapping.

### Examples

See the examples for [Insert\(\)](#) and [Join\(\)](#).

## Options methods

### Options::GetValue( char opt, int subopt )

Returns the value of a flag previously stored by [Options::Parse\(\)](#).

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Options</a>	
<b>Arguments</b>	char opt	The flag to check
	int subopt	Return the argument associated with the <b>subopt</b> -th occurrence of the <b>opt</b> flag on the command line.
<b>Returns</b>	StrPtr *	The value of the flag. This is “true” for flags which, when provided, do not take a value, and <b>NULL</b> if the flag is not provided

### Notes

You must call [Options::Parse\(\)](#) before calling [GetValue\(\)](#).

If a flag does not occur on the command line, [GetValue\(\)](#) returns **NULL**.

If a flag is provided without a value, [GetValue\(\)](#) returns “true”.

If a flag appears only once on a command line, extract the value of its arguments by calling [GetValue\(\)](#) with a **subopt** of zero, or use the `[]` operator.

If a flag occurs more than once on a command line, extract the value supplied with each occurrence by calling [Options::GetValue\(\)](#) once for each occurrence, using different **subopt** values.

### See also

[Options::Parse\(\)](#) [Options::operator\[\]](#)

### Example

Executing the following code produces the following output:

```
$ getvalue -h -c1 -c2 -d3

opts.GetValue( h, 0 ) value is true
opts.GetValue( c, 0 ) value is 1
opts.GetValue( c, 1 ) value is 2
opts.GetValue( d, 0 ) value is 3
```

```
#include <stdhdrs.h>
#include <strbuf.h>
#include <error.h>
#include <options.h>

int main( int argc, char **argv )
{
    // Parse options.
    Error *e = new Error();
    ErrorId usage = { E_FAILED, "Usage: getvalue -h for usage." };

    Options opts;

    // strip out the program name before parsing
    argc--;
    argv;

    char *ParseOpts = "ha:b:c:d:e:f:";
    opts.Parse( argc, argv, ParseOpts, OPT_ANY, usage, e );

    if ( e->Test() )
    {
        StrBuf msg;
        e->Fmt( &msg ); // See Error::Fmt()
        printf( "ERROR:\n%s", msg.Text() );
        return 1;
    }

    char *iParseOpts = ParseOpts;
    int isubopt;
    StrPtr *s;

    // Print values for options.
    while( *iParseOpts != '\0' )
    {
        if ( *iParseOpts != ':' )
        {
            isubopt = 0;
            while( s = opts.GetValue( *iParseOpts, isubopt ) )
            {
                printf( "opts.GetValue( %c, %d ) value is %s\n",
                    *iParseOpts, isubopt, s->Text() );
                isubopt++;
            }
        }
        iParseOpts++;
    }
    return 0;
}
```

## Options::operator[]( char opt )

Returns the value of a flag previously stored by [Options::Parse\(\)](#).

Virtual?	No	
Class	<a href="#">Options</a>	
Arguments	char opt	The flag to check

### Notes

You must call [Options::Parse\(\)](#) before using the [] operator.

If a flag does not occur on the command line, the [] operator returns **NULL**.

If a flag is provided without a value, the [] operator returns “true”.

If a flag appears once on a command line, the [] operator returns its argument. This is equivalent to calling [Options::GetValue\(\)](#) with a *subopt* of zero.

The [] operator is sufficient for extracting the value of any flag which does not have more than one value associated with it. If a flag appears more than once on the same command line, you must use [Options::GetValue\(\)](#), specifying a different *subopt* value for each appearance.

### See also

[Options::Parse\(\)](#) [Options::GetValue\(\)](#)

### Example

The following code parses some of the standard Perforce global options and stores them in a `ClientApi` object.

If the `-h` option is supplied, the program also displays a brief message.

```
#include <iostream>
#include <clientapi.h>
#include <error.h>
#include <errornum.h>
#include <msgclient.h>
#include <options.h>

int main( int argc, char **argv )
{
    Error *e = new Error();
    ErrorId usage = { E_FAILED, "Usage: myapp -h for usage." };

    // Bypass argv[0] before parsing
    argc--;
    argv++;

    Options opts;
    opts.Parse( argc, argv, "hc:H:d:u:p:P:", OPT_ANY, usage, e );

    if ( e->Test() )
    {
        StrBuf msg;
        e->Fmt( &msg ); // See Error::Fmt()
        printf( "Error: %s", msg.Text() );
        return 1;
    }

    ClientApi client;
    StrPtr *s;

    // Get command line overrides of client, host, cwd, user, port, pass
    if ( s = opts[ 'h' ] ) printf ( "User asked for help\n" );
    if ( s = opts[ 'c' ] ) client.SetClient ( s );
    if ( s = opts[ 'H' ] ) client.SetHost ( s );
    if ( s = opts[ 'd' ] ) client.SetCwd ( s );
    if ( s = opts[ 'u' ] ) client.SetUser ( s );
    if ( s = opts[ 'p' ] ) client.SetPort ( s );
    if ( s = opts[ 'P' ] ) client.SetPassword ( s );

    // Perform desired operation(s) with your ClientApi here
    return 0;
}
```

**Options::Parse( int &, char \*\* &, const char \*, int, const ErrorId &, Error \* )**

Manipulate `argc` and `argv` to extract command line arguments and associated values.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Options</a>	
<b>Arguments</b>	<code>int &amp;argc</code>	Number of arguments
	<code>char ** &amp;argv</code>	An array of arguments to parse
	<code>const char *opts</code>	The list of valid options to extract
	<code>int flag</code>	A flag indicating how many arguments are expected to remain when parsing is complete
	<code>const ErrorId &amp;usage</code>	An error message containing usage tips
	<code>Error *e</code>	The <code>Error</code> object to collect any errors encountered
<b>Returns</b>	<code>void</code>	

**Notes**

You must bypass `argv[0]` (that is, the name of the calling program) before calling [Options::Parse\(\)](#). This is most easily done by decrementing `argc` and incrementing `argv`.

An argument may be of the form `-avalue` or `-a value`. Although an argument of the form `-a value` is passed as two entries in `argv`, the [Options::Parse\(\)](#) method parses it as one logical argument.

As arguments are scanned from the caller's `argv`, the caller's `argc` and `argv` are modified to reflect the arguments scanned. Scanning stops when the next argument either:

- does not begin with a `-`, or
- is a `-` only, or
- is not in the array of expected options.

Once scanning has stopped, `argc` and `argv` are returned "as-is"; that is, they are returned as they were when scanning stopped. There is no "shuffling" of arguments.

The `opts` argument is a format string indicating which options are to be scanned, and whether these options are to have associated values supplied by the user. Flags with associated values must be followed by a colon (":") or a period (".") in the format string. Using a colon allows arguments to be specified in the form `-avalue` or `-a value`; using a period allows only the `-avalue` form.

If, based on the expectation set in the format string, the actual option string in `argv` does not provide a value where one is expected, an error is generated.

For instance, the **p4** Command Line Client's `-V` and `-?` flags are expected to be supplied without values, but the `-p` flag is expected to be accompanied with a setting for **P4PORT**. This is the format string used by the **p4** Command Line Client:

```
"?c:C:d:GRhH:p:P:l:L:su:v:Vx:z:Z:"
```

Characters followed by colons (**c**, **C**, and so on) are command line flags that take values; all characters not followed by colons (**?**, **G**, **R**, **h**, **s**, and **V**) represent command line flags that require no values.

There is a limit of 20 options per command line, as defined in `options.h` by the constant `N_OPTS`.

The `flag` argument should be one of the following values (defined in `options.h`):

Argument	Value	Meaning
<code>OPT_ONE</code>	<code>0x01</code>	Exactly one argument is expected to remain after parsing
<code>OPT_TWO</code>	<code>0x02</code>	Exactly two arguments are expected to remain after parsing
<code>OPT_THREE</code>	<code>0x04</code>	Exactly three arguments are expected to remain after parsing
<code>OPT_MORE</code>	<code>0x08</code>	More than two arguments (three or more) are to remain after parsing
<code>OPT_NONE</code>	<code>0x10</code>	Require that zero arguments remain after parsing; if arguments remain after parsing, set an error.
<code>OPT_MAKEONE</code>	<code>0x20</code>	If no arguments remain after parsing, create one that points to <b>NULL</b> .
<code>OPT_OPT</code>	<code>0x11</code>	<b>NONE</b> , or <b>ONE</b> .
<code>OPT_ANY</code>	<code>0x1F</code>	<b>ONE</b> , <b>TWO</b> , <b>THREE</b> , <b>MORE</b> , or <b>NONE</b> .
<code>OPT_DEFAULT</code>	<code>0x2F</code>	<b>ONE</b> , <b>TWO</b> , <b>THREE</b> , <b>MORE</b> , or <b>MAKEONE</b> .
<code>OPT_SOME</code>	<code>0x0F</code>	<b>ONE</b> , <b>TWO</b> , <b>THREE</b> , or <b>MORE</b> .

## See also

[Options::GetValue\(\)](#) [Options::operator\[\]\(\)](#)

## Example

The following code and examples illustrate how [Options::Parse\(\)](#) works.



```

#include <stdhdrs.h>
#include <strbuf.h>
#include <error.h>
#include <options.h>

int main( int argc, char **argv )
{
    // Parse options.
    Error *e = new Error();
    ErrorId usage = { E_FAILED, "Usage: parse optionstring flag args" };

    Options opts;

    // strip out the program name before parsing
    argc--;
    argv;

    // next argument is options to be parsed
    char *ParseOpts = argv[ 0 ];
    argc--;
    argv;

    // next argument is number of arguments remaining after parse
    int flag = strtol( argv[ 0 ], NULL, 0 );
    argc--;
    argv;

    // Echo pre-parse values
    int iargv;
    printf( "Prior to Options::Parse call:\n" );
    printf( " ParseOpts is %s\n", ParseOpts );
    printf( " flag is 0x%2.2X\n", flag );
    printf( " argc is %d\n", argc );
    for ( iargv = 0; iargv &lt;&lt; argc; iargv )
    {
        printf( " argv[ %d ] is %s\n", iargv, argv[ iargv ] );
    }
    printf( "\n" );

    opts.Parse( argc, argv, ParseOpts, flag, usage, e );
    if ( e->Test() )
    {
        // See example for Error::Fmt()
        StrBuf msg;
        e->Fmt( &msg );
        printf( "ERROR:\n%s\n", msg.Text() );
    }

    char *iParseOpts = ParseOpts;
    int isubopt;
    StrPtr *s;

    // Print values for options.
    while( *iParseOpts != '\0' )
    {
        if ( *iParseOpts != ':' )
        {
            isubopt = 0;
            while( s = opts.GetValue( *iParseOpts, isubopt ) )
            {
                printf( "opts.GetValue( %c, %d ) value is %s\n",
                    *iParseOpts, isubopt, s->Text() );

                isubopt++;
            }
        }
        iParseOpts++;
    }
}

```

Invoke `parsedemo` with a format string, a flag (as defined in `options.h`) to specify the number of options expected, and a series of arguments.

For instance, to allow arguments `-a`, `-b` and `-c`, where `-a` and `-b` take values, but `-c` does not take a value, and to use a flag of `OPT_NONE (0x10)` to require that no options remain unparsed after the call to `Options::Parse()`, invoke `parsedemo` as follows.

```
$ parsedemo a:b:c 0x10 -a vala -b valb -c
```

Arguments of the form `-c one` are passed as two entries in `argv`, but parsed as one logical argument:

```
$ parsedemo ha:b:c:d:e: 0x10 -cone
Prior to Options::Parse call:
  ParseOpts is ha:b:c:d:e:
  flag is 0x10
  argc is 1
  argv[ 0 ] is -cone

opts.GetValue( c, 0 ) value is one

After Options::Parse call:
  argc is 0

$ parsedemo ha:b:c:d:e: 0x10 -c one
Prior to Options::Parse call:
  ParseOpts is ha:b:c:d:e:
  flag is 0x10
  argc is 2
  argv[ 0 ] is -c
  argv[ 1 ] is one

opts.GetValue( c, 0 ) value is one

After Options::Parse call:
  argc is 0
```

Use of a period in the options string disallows the `-c one` form for the `c` option:

```

$ parsedemo ha:b:c:d:e: 0x10 -c one
Prior to Options::Parse call:
  ParseOpts is ha:b:c:d:e:
  flag is 0x10
  argc is 2
  argv[ 0 ] is -c
  argv[ 1 ] is one

ERROR:
Usage: parse optionstring flag args
Unexpected arguments.

opts.GetValue( c, 0 ) value is

After Options::Parse call:
  argc is 1
  argv[ 0 ] is one

```

Arguments not in the format string are permitted or rejected with the use of different flag values; `OPT_NONE` (0x10) requires that no arguments remain after the call to [Options::Parse\(\)](#), while `OPT_ONE` (0x01) requires that one argument remain.

```

$ parsedemo ha:b:c:d:e: 0x10 -c one two
Prior to Options::Parse call:
  ParseOpts is ha:b:c:d:e:
  flag is 0x10
  argc is 3
  argv[ 0 ] is -c
  argv[ 1 ] is one
  argv[ 2 ] is two

ERROR:
Usage: parse optionstring flag args
Unexpected arguments.

opts.GetValue( c, 0 ) value is one

$ parse ha:b:c:d:e: 0x01 -c one two
Prior to Options::Parse call:
  ParseOpts is ha:b:c:d:e:
  flag is 0x01
  argc is 3
  argv[ 0 ] is -c
  argv[ 1 ] is one
  argv[ 2 ] is two

opts.GetValue( c, 0 ) value is one

After Options::Parse call:
  argc is 1
  argv[ 0 ] is two

```

**Options::Parse( int &, StrPtr \* &, const char \*, int, const ErrorId &, Error \* )**

Extract command line arguments and associated values.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Options</a>	
<b>Arguments</b>	<code>int &amp;argc</code>	Number of arguments
	<code>StrPtr * &amp;argv</code>	An array of arguments to parse
	<code>const char *opts</code>	The list of valid options to extract
	<code>int flag</code>	A flag indicating how many arguments are expected to remain when parsing is complete
	<code>const ErrorId &amp;usage</code>	An error message containing usage tips
	<code>Error *e</code>	The <code>Error</code> object to collect any errors encountered
<b>Returns</b>	<code>void</code>	

**Notes**

See the notes for the `char ** &argv` version of [Options::Parse\(\)](#) for details.

**See also**

[Options::Parse\(\)](#)

## ServerHelperApi methods

---

### ServerHelperApi::ClearProtocol()

Clear any protocol variables set using [ServerHelperApi::SetProtocol](#)

Virtual?	No
Class	<a href="#">ServerHelperApi</a>
Arguments	None
Returns	void

#### Notes

[ClearProtocol\(\)](#) unsets any protocol variables previously set using [SetProtocol\(\)](#) or [SetProtocolV\(\)](#).  
Calling [ClearProtocol\(\)](#)

## ServerHelperApi::CloneFromRemote(int,const StrPtr\*,ClientUser\*,Error\*)

Populates a personal server based on a remote specification.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ServerHelperApi</a>	
<b>Arguments</b>	<code>int depth</code>	specifies the number of revisions to fetch of each file
	<code>const StrPtr *df</code>	optional debug flag; set to 0 to leave it unset
	<code>ClientUser *ui</code>	a pointer to <code>ClientUser</code> object
	<code>Error *e</code>	a pointer to an <code>Error</code> object
<b>Returns</b>	<code>int</code>	indicates success of command

### Notes

This method stores the remote generated by either [PrepareToCloneFilepath\(\)](#) or [PrepareToCloneRemote\(\)](#) as `origin` and then runs `p4 fetch` to populate the local server. This method should be run against the instance of `ServerHelperApi` class configured as the personal server.

A return value of 1 indicates a successful clone. If the method returns 0, check the `Error` object to see what occurred.

### See also

[ServerHelperApi::PrepareToCloneFilepath\(\)](#) [ServerHelperApi::PrepareToCloneRemote\(\)](#)

## Example

```
// Basic "p4 clone" flow:
ClientUser ui;
Error e;
ServerHelperApi personalServer( &e );

if( e.Test() )
    return 0;

personalServer.SetDvcsDir( "/path/to/root", &e );
personalServer.SetProg( "MyApp" ); // optional
personalServer.SetVersion( "version" ); // optional

if( personalServer.Exists() )
    return 0;

ServerHelperApi sharedServer( &e );
sharedServer.SetPort( "1666" );
sharedServer.SetProg( "MyApp" ); // optional
sharedServer.SetVersion( "version" ); // optional

// Fetch the remote spec
if( !personalServer.PrepareToCloneRemote( &sharedServer, remote, &ui ) )
    return 0;

// Create the personal server
// This returns the exit code from p4d, so 0 is success
if( personalServer.InitLocalServer( &ui ) )
    return 0;

// Fetch from the remote
if( !personalServer.CloneFromRemote( 0, 0, &ui ) )
    return 0;
```

## ServerHelperApi::CloneFromRemote(int,const char\*,ClientUser\*,Error\*)

Populates a personal server based on a remote specification.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ServerHelperApi</a>	
<b>Arguments</b>	<code>int depth</code>	specifies the number of revisions to fetch for each file
	<code>const char *df</code>	optional debug flag; set to 0 to leave it unset
	<code>ClientUser *ui</code>	a pointer to a <code>ClientUser</code> object
	<code>Error *e</code>	a pointer to an <code>Error</code> object
<b>Returns</b>	<code>int</code>	indicates success of command

### Notes

See the notes for the `StrPtr*` version of [CloneFromRemote\(\)](#) for details.



## ServerHelperApi::CopyConfiguration(ServerHelperApi\*,ClientUser\*,Error\*)

Copies server configuration information from a shared server in preparation for creating a matching personal server.

Virtual?	No	
Class	<a href="#">ServerHelperApi</a>	
Arguments	ServerHelperApi* remote	the shared server to copy settings from
	ClientUser *ui	pointer to a ClientUser object
	Error *e	pointer to an Error object
Returns	int	

### Notes

This method gets the case sensitivity and Unicode settings from a shared server. For a personal server to push and fetch against a shared server it must have matching case sensitivity and Unicode settings. Call this method prior to running [InitLocalServer\(\)](#) to ensure that the new personal server will work properly with the shared server. This method can only be run if the personal server does not exist. Use the [Exists\(\)](#) method to test to see if the personal server already exists.

### Example

```
// Discover the case sensitivity and unicode settings
if( !personalServer.CopyConfiguration( &centralServer, &ui, &e ) )
    return 1;

// Create the local server
if( personalServer.InitLocalServer( &ui, &e ) )
    return 1;
```

## ServerHelperApi::Exists(ClientUser\*,Error\*)

Checks for the existence of a personal server.

Virtual?	No	
Class	<a href="#">ServerHelperApi</a>	
Arguments	ClientUser * ui	A ClientUser object
Returns	int	returns 1 if a personal server exists in the root dir

### Notes

Many `ServerHelperApi` methods expect there to be no existing server in the path set by [SetDvcsDir\(\)](#). `Exists()` is useful for avoiding potential errors caused by pre-existing servers.

### Example

```
// Check that we don't already have a DVCS tree at the target directory
personalServer.SetDvcsDir( "/User/home/dev", &e );
if( e.Test() )
    return 1;

if( personalServer.Exists( &ui, &e ) )
    return 1;
```

## ServerHelperApi::GetCaseFlag()

Gets the currently set case sensitivity flag value.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ServerHelperApi</a>	
<b>Arguments</b>	None	
<b>Returns</b>	StrPtr	returns '-C0' or '-C1' or an empty StrPtr

### Notes

Call after running [CopyConfiguration\(\)](#) or [SetCaseFlag\(\)](#) to see the value that will be used when initializing the personal server.

### See also

[ServerHelperApi::GetUnicode\(\)](#)

## ServerHelperApi::GetClient()

Get the client workspace associated with this connection.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr&amp;</code> the current client workspace name

### Notes

This method has the same behavior as the [ClientApi::GetClient\(\)](#) method.

## ServerHelperApi::GetClient(Error\*)

Creates and initializes a ClientApi object for the specified server

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ServerHelperApi</a>	
<b>Arguments</b>	<b>Error *e</b>	a pointer to an Error object
<b>Returns</b>	<b>ClientApi* client</b>	if successful, an initialized ClientApi object; otherwise 0

### Notes

This is a convenience method to get a `ClientApi` object against the server associated with the `ServerHelperApi` object. `GetClient()` is the equivalent of creating a new `ClientApi` object, setting the `P4PORT`, `P4CLIENT`, and `P4USER`, and then running [ClientApi::Init\(\)](#). As with [ClientApi::Init\(\)](#), protocol variables must be set using [SetProtocol\(\)](#) before running `GetClient()`.

### See also

[ClientApi::Init\(\)](#)

### Example

```
// Create personal server
personalServer.CloneFromRemote( 0, 0, debug, &ui, &e )

// Turn on tagged output for the client
personalServer.SetProtocolV( P4Tag::v_tag );

// Get an init'ed ClientApi object
ClientApi *client = personalServer.GetClient( &e );
if( !client )
    return 1;

// Run 'p4 info'
client->RunTag( "info", &ui );
```

## ServerHelperApi::GetDvcsDir()

Get the path to root of the personal server.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> the root path of the personal server

### Notes

See `ClientApi::GetClient()` for more about the `StrPtr` return value.

## ServerHelperApi::GetPort()

Get the connection information for this server.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> the hostname and port for the server

### Notes

See `ClientApi::GetClient()` for more about the `StrPtr` return value.

## ServerHelperApi::GetProg()

Get the application name set in the 'prog' variable.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	None
<b>Returns</b>	const StrPtr & the name of your application

### Notes

See [ClientApi::GetClient\(\)](#) for more about the StrPtr return value.

### See also

[ServerHelperApi::SetProg\(\)](#)



## ServerHelperApi::GetQuiet()

Checks whether quiet output is enabled.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	None
<b>Returns</b>	int      returns 1 if quiet output is enabled

### Notes

If quiet is enabled, the output from clone and init are greatly reduced.

## ServerHelperApi::GetUnicode()

Return the Unicode flag setting.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	None
<b>Returns</b>	int returns 1 if unicode is enabled

### Notes

When a personal server is initialized it can either be in Unicode mode or not. If set to use Unicode mode all filenames and metadata will be translated from the code page used by the local machine into UTF-8. To be able to push or fetch, a personal server must match the Unicode setting of the shared server. Use the [CopyConfiguration\(\)](#) method to copy the Unicode and case-sensitivity settings from the shared before initializing the personal server.

### See also

[ServerHelperApi::GetCaseFlag\(\)](#)

## ServerHelperApi::GetUser()

Get the user name that is currently associated with the server connection.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> the active user name

### Notes

See `ClientApi::GetClient()` for more about the `StrPtr` return value.

## ServerHelperApi::GetVersion()

Get the application name set in the 'version' variable

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	None
<b>Returns</b>	<code>const StrPtr &amp;</code> the version of your application

### Notes

See `ClientApi::GetClient()` for more about the `StrPtr` return value.

### See also

[ServerHelperApi::GetProg\(\)](#)

## ServerHelperApi::InitLocalServer(ClientUser\*,Error\*)

Creates the personal server based on configured settings.

Virtual?	No	
Class	<a href="#">ServerHelperApi</a>	
Arguments	ClientUser *ui	a ClientUser object
	Error *e	an Error object
Returns	int	returns the <code>p4d</code> return value; 0 indicates success

### Notes

This method does the work of creating the personal server using the settings that have been previously set on the `ServerHelperApi` object. As part of creating the personal server it writes the `P4CONFIG` and `P4IGNORE` files, creates the `.p4root` dir, sets the case sensitivity and Unicode flags, creates the requisite `serverId` and `server spec`, and generates a protect table to restrict access to `localhost`.

If you are cloning from an existing shared server you will need to follow your call to `InitLocalServer()` with a call to `CloneFromRemote()`. `InitLocalServer()` only creates the personal server, it does not populate it.

### Example

```
ClientUser ui;
Error e;
ServerHelperApi server( &e );

if( e.Test() )
    return 0;

server.SetDvcsDir( "/path/to/dvcs" );
server.SetProg( "MyApp" ); // optional
server.SetVersion( "version" ); // optional

if( server.Exists() )
    return 0;

// The unicode and case-sensitivity options must be set _before_
// InitLocalServer() is called. These can be set manually or
// discovered.

server.SetUnicode( true );
server.SetCaseSensitivity( "-C0" );

if( !server.InitLocalServer( &ui ) )
    return 0;
```

## ServerHelperApi::PrepareToCloneFilepath(ServerHelperApi\*,const char\*,ClientUser\*,Error\*)

Creates a remote specification based on the provided filepath.

Virtual?	No	
Class	<a href="#">ServerHelperApi</a>	
Arguments	ServerHelperApi *remote	ServerHelperApi object representing the shared server
	const char *path	depot path to clone
	Error *e	an Error object
Returns	int	returns 1 if successful

### Notes

This creates a new remote spec based on the provided filepath. It also checks that **p4 fetch** is allowed on the remote server specified.

### See also

[ServerHelperApi::PrepareToCloneRemote\(\)](#)

### Example

```
ServerHelperApi remoteServer( &e );
remoteServer.SetPort( "1666" );
remoteServer.SetProg( "MyApp" ); // optional
remoteServer.SetVersion( "1.0" ); // optional

// Generate the remote spec
if( !localServer.PrepareToCloneFilepath( &remoteServer, path, &ui ) )
    return 0;

// Create the local server
// This returns the exit code from p4d, so 0 is success
if( localServer.InitLocalServer( &ui ) )
    return 0;

// Fetch from the remote
if( !localServer.CloneFromRemote( 0, 0, &ui ) )
    return 0;
```

## ServerHelperApi::PrepareToCloneFilepath(ServerHelperApi\*,const StrPtr\*,ClientUser\*,Error\*)

Creates a remote specification based on the provided filepath.

Virtual?	No	
Class	<a href="#">ServerHelperApi</a>	
Arguments	ServerHelperApi *remote	ServerHelperApi object representing the shared server
	const StrPtr *path	depot path to clone
	Error *e	a pointer to an Error object
Returns	int	returns 1 if successful

### Notes

See the `const char *` version of [PrepareToCloneFilepath\(\)](#) for usage details.

## ServerHelperApi::PrepareToCloneRemote(ServerHelperApi\*,const char\*,ClientUser\*,Error\*)

Creates a remote specification based on the provided remote from the shared server.

Virtual?	No	
Class	<a href="#">ServerHelperApi</a>	
Arguments	ServerHelperApi *remote	ServerHelperApi object representing the shared server
	const char *remote	name of remote spec on shared server
	Error *e	a pointer to an Error object
Returns	int	returns 1 if successful

### Notes

This creates a new remote spec based on the provided remote spec stored on the shared server. It also checks that `p4 fetch` is allowed on the remote server specified.

### See also

[ServerHelperApi::PrepareToCloneFilepath\(\)](#)

### Example

```
ServerHelperApi remoteServer( &e );
remoteServer.SetPort( "1666" );
remoteServer.SetProg( "MyApp" ); // optional
remoteServer.SetVersion( "1.0" ); // optional

// Copy the remote spec from the shared server
if( !localServer.PrepareToCloneFilepath( &remoteServer, remote, &ui ) )
    return 0;

// Create the local server
// This returns the exit code from p4d, so 0 is success
if( localServer.InitLocalServer( &ui ) )
    return 0;

// Fetch from the remote
if( !localServer.CloneFromRemote( 0, 0, &ui ) )
    return 0;
```



## ServerHelperApi::PrepareToCloneRemote(ServerHelperApi\*,const StrPtr\*,ClientUser\*,Error\*)

Creates a remote specification based on the provided remote from the shared server.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ServerHelperApi</a>	
<b>Arguments</b>	ServerHelperApi *remote	ServerHelperApi object representing the shared server
	const StrPtr *remote	name of remote spec on shared server
	Error *e	a pointer to an Error object
<b>Returns</b>	int	returns 1 if successful

### Notes

See the `const char *` version of [PrepareToCloneRemote\(\)](#) for details.

### See also

[ServerHelperApi::PrepareToCloneFilepath\(\)](#)

## ServerHelperApi::SetCaseFlag(const char\*,Error\*)

Sets the case flag for an uninitialized personal server.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const char *flag</code> the case sensitivity value
	<code>Error *e</code> pointer to an Error object
<b>Returns</b>	<code>void</code>

### Notes

This sets the case sensitivity flag used when initializing a personal server. It can be set to '-C0' or '-C1'; '-C0' indicates the server is case-sensitive while '-C1' causes the server to be case-insensitive.

### See also

[ServerHelperApi::SetUnicode\(\)](#)

## ServerHelperApi::SetCaseFlag(const StrPtr\*,Error\*)

Sets the case flag for an uninitialized personal server.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ServerHelperApi</a>	
<b>Arguments</b>	<code>const StrPtr *flag</code>	the case sensitivity value
	<code>Error *e</code>	pointer to an Error object
<b>Returns</b>	<code>void</code>	

### Notes

See the `const char *` version of [GetCaseFlag\(\)](#) for usage details.

## ServerHelperApi::SetClient(const char\*)

Sets the client workspace.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const char *name</code> the name of the client workspace
<b>Returns</b>	<code>void</code>

### Notes

Sets the client workspace that should be used when connecting to the server.

## ServerHelperApi::SetClient(const StrPtr\*)

Sets the client workspace.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const StrPtr *name</code> the name of the client workspace to use
<b>Returns</b>	<code>void</code>

### Notes

Sets the client workspace that should be used when connecting to the server.

## ServerHelperApi::SetDefaultStream(const char\*)

Sets the default stream name for the personal server.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const char *name</code> the name of the stream
<b>Returns</b>	<code>void</code>

### Notes

Sets the name of the stream to create when initializing the personal server. This is the equivalent of the '-c' flag when using the command line interface. Running [PrepareToCloneRemote\(\)](#) will override the value set by [SetDefaultStream\(\)](#).

## ServerHelperApi::SetDefaultStream(const StrPtr\*)

Sets the default stream name for the personal server.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const StrPtr *name</code> the name of the stream
<b>Returns</b>	<code>void</code>

### Notes

See the `const char *` version of [SetDefaultStream\(\)](#) for usage details.

## ServerHelperApi::SetDvcsDir(const char\*)

Sets the root dir for the personal server.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ServerHelperApi</a>	
<b>Arguments</b>	<code>const char *path</code>	full path to the root directory
	<code>Error *e</code>	an Error object
<b>Returns</b>	<code>int</code>	returns 0 if there is an error, 1 if successful

### Notes

Sets the directory that will be used to hold the personal server. The directory should not already have a personal server in it or [InitLocalServer\(\)](#) will fail. [SetDvcsDir\(\)](#) does not check for an existing server; use the [Exists\(\)](#) method after running [SetDvcsDir\(\)](#) to test for an existing personal server.



## ServerHelperApi::SetDvcsDir(const StrPtr\*)

Sets the root dir for the personal server.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ServerHelperApi</a>	
<b>Arguments</b>	<code>const StrPtr</code>	full path to the root directory
	<code>*path</code>	
	<code>Error *e</code>	an Error object
<b>Returns</b>	<code>int</code>	returns 0 if there is an error, 1 if successful

### Notes

See the `const char *` version of [SetDvcsDir\(\)](#) for usage details.

## ServerHelperApi::SetPort(const char\*)

Sets the server connection information.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const char *port</code> the hostname and port to connect to
<b>Returns</b>	<code>void</code>

### Notes

Sets the hostname and port that will be connected to. It should be of the form 'hostname:port' such as 'helix.perforce.com:1666'.

## ServerHelperApi::SetPort(const StrPtr\*)

Sets the server connection information.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const StrPtr *name</code> the hostname and port to connect to
<b>Returns</b>	<code>void</code>

### Notes

Sets the hostname and port that will be connected to. It should be of the form 'hostname:port' such as 'helix.perforce.com:1666'.

## ServerHelperApi::SetProg(const char\*)

Sets the program name for your application.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const char *name</code> the name of your application
<b>Returns</b>	<code>void</code>

### Notes

Sets the program name for your application. This name will show up in the logs of any server your application runs against. Setting a program name makes it much easier to identify tools which are not running properly and is highly recommended.

## ServerHelperApi::SetProg(const StrPtr\*)

Sets the program name for your application.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const StrPtr *name</code> the name of your application
<b>Returns</b>	<code>void</code>

### Notes

See the `const char *` version of [SetProg\(\)](#) for usage details.

## ServerHelperApi::SetProtocol(const char\*,const char\*)

Adds protocol tags for the [ServerHelperApi::GetClient\(\)](#) method.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ServerHelperApi</a>	
<b>Arguments</b>	<code>const char *p</code>	the protocol being set
	<code>const char *v</code>	the value to set
<b>Returns</b>	<code>void</code>	

### Notes

See [SetProtocol\(\)](#) on ClientApi for details.

## ServerHelperApi::SetProtocolV(const char\*)

Adds protocol tags for the [ServerHelperApi::GetClient\(\)](#) method.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const char *p</code> a single string with the protocol to set and the value
<b>Returns</b>	<code>void</code>

### Notes

See [SetProtocolV](#) on `ClientApi` for details.

## ServerHelperApi::SetQuiet()

Enables reduced output for clone and init.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	none
<b>Returns</b>	void

### Notes

Disables informational messages when running [CloneFromRemote\(\)](#).



## ServerHelperApi::SetUnicode(int)

Sets or unsets the Unicode flag on the personal server.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">ServerHelperApi</a>	
<b>Arguments</b>	int	set to 1 to enable Unicode in the personal server
<b>Returns</b>	void	

### Notes

This method is used to enable Unicode mode when initializing a personal server. This method needs to be called before calling [InitLocalServer\(\)](#). The Unicode setting of the personal server must match the Unicode setting of any shared servers it will push or fetch content to. [CopyConfiguration\(\)](#) can be used to ensure the personal server matches the settings of the shared server.

## ServerHelperApi::SetUser(const char\*)

Sets the user account for connecting to the server.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const char *name</code> the user name
<b>Returns</b>	<code>void</code>

### Notes

Sets the user name for connecting to the associated server. The user must have permission to access any files being cloned from the shared server.

## ServerHelperApi::SetUser(const StrPtr\*)

Sets the user account for connecting to the server.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const StrPtr *name</code> the user name to use
<b>Returns</b>	<code>void</code>

### Notes

See the `const char *` version of [SetUser\(\)](#) for usage details.

## ServerHelperApi::SetVersion(const char\*)

Sets the version string for your application.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const char *version</code> the version information for your application
<b>Returns</b>	<code>void</code>

### Notes

Sets the version string for your application. This version will show up in the logs of any server your application runs against. Setting a version makes it much easier to identify tools which are not running properly and is highly recommended.

### See also

[ServerHelperApi::SetProg\(\)](#)

## ServerHelperApi::SetVersion(const StrPtr\*)

Sets the version string for your application.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">ServerHelperApi</a>
<b>Arguments</b>	<code>const StrPtr *name</code> the version information for your application
<b>Returns</b>	<code>void</code>

### Notes

See the `const char *` version of [SetVersion\(\)](#) for usage details.

## Signaler methods

### Signaler::Block()

Cause interrupt signals from the user to be ignored until a subsequent call to [Signaler::Catch\(\)](#).

Virtual?	No
Class	<a href="#">Signaler</a>
Arguments	None
Returns	void

### Notes

[Block\(\)](#) does not actually block the signals, but causes the process to ignore them.

For portability reasons, [Block\(\)](#) and [Catch\(\)](#) use the BSD/ANSI C `signal(2)` function rather than the POSIX `sigaction()`.

### See also

[Signaler::Catch\(\)](#) [Signaler::OnIntr\(\)](#)

### Example

```
#include <unistd.h> // for sleep()
#include <stdhdrs.h>
#include <strbuf.h>
#include <signaler.h>

int main( int argc, char **argv )
{
    // Block ^C
    printf( "For the next 5 seconds, ^C will be ignored\n" );
    signaler.Block();
    sleep( 5 );

    printf( "Enabling ^C again\n" );
    signaler.Catch();
    for ( ; ; )
        sleep( 60 );
    exit( 0 );
}
```

## Signaler::Catch()

Allow interrupt signals from the user to be delivered once more following a previous call to [Signaler::Block\(\)](#).

Virtual?	No
Class	<a href="#">Signaler</a>
Arguments	None
Returns	void

### Notes

[Catch\(\)](#) does not replace your signal handler if you have already replaced the `Signaler` class' handler with one of your own using the ANSI `signal(2)` function.

For portability reasons, [Block\(\)](#) and [Catch\(\)](#) use the BSD/ANSI C `signal(2)` function rather than the POSIX `sigaction()`.

### See also

[Signaler::Block\(\)](#) [Signaler::OnIntr\(\)](#)

### Example

```
int main( int argc, char **argv )
{
    // Block ^C
    printf( "For the next 5 seconds, ^C will be ignored\n" );
    signaler.Block();
    sleep( 5 );

    printf( "Enabling ^C again\n" );
    signaler.Catch();
    for ( ; ; )
        sleep( 60 );
    exit( 0 );
}
```

## Signaler::DeleteOnIntr( void \* )

Removes a function previously registered using [OnIntr\(\)](#) from the list.

Virtual?	No	
Class	<a href="#">Signaler</a>	
Arguments	void *ptr	Pointer to the data item with which the original function was registered
Returns	void	

### See also

[Signaler::OnIntr\(\)](#) [Signaler::Intr\(\)](#)



**Example**

```

#include <unistd.h> // for sleep()
#include <stdhdrs.h>
#include <strbuf.h>
#include <signaler.h>

class MyClass
{
public:
void      Set( StrPtr *d ) { data = *d; }
const StrPtr *Get()      { return &data; }
void      Identify()     { printf( "I'm %s\n", data.Text() ); }

private:
StrBuf    data;
};

static void InterruptHandler( void *p )
{
MyClass   *m = ( MyClass * )p;
m->Identify();
}

int main( int argc, char **argv )
{
StrBuf    data;
MyClass   *list[ 5 ];

for ( int i = 1; i <= 5; i++ )
{
data.Set( "Object" );
data << i;

MyClass   *p = new MyClass;
list[ i - 1 ] = p;

p->Set( &data );

signaler.OnIntr( InterruptHandler, (void *)p );
}

// Unregister Object 3
signaler.DeleteOnIntr( list[ 2 ] );

printf( "Hit ^C to fire the interrupt handler\n" );
for ( ; ; )
sleep( 60 );

exit( 0 );
}

```

## Signaler::Intr()

Coordinate execution of all functions registered by [Signaler::OnIntr\(\)](#).

Virtual?	No
Class	<a href="#">Signaler</a>
Arguments	None
Returns	void

### Notes

[Intr\(\)](#) is the `Signaler` class's main handler for interrupt signals.

Most Perforce client applications do not need to call [Intr\(\)](#) directly, because it is called directly from the internal handler function that catches the interrupt signals.

This internal handler function also causes the process to exit, returning an exit status of -1 to the operating system. (For instance, `signaler.Intr(); exit( -1 )`)

If you require more flexible or complex interrupt handling, replace the default interrupt handler function with your own by using the ANSI C `signal(2)` function, and call [Intr\(\)](#) to execute the registered functions.

### Caveat

[Intr\(\)](#) does not deregister functions after they have been called. When calling a registered function twice might cause a failure, immediately deregister it using [DeleteOnIntr\(\)](#) after the function has been called.

### See also

[Signaler::OnIntr\(\)](#)

**Example**

```

#include <unistd.h>    // for sleep()
#include <signal.h>
#include <stdhdrs.h>
#include <strbuf.h>
#include <signaler.h>

class MyClass
{
public:
    void      Set( StrPtr *d ) { data = *d; }
    const StrPtr *Get()      { return &data; }
    void      Identify()     { printf( "I'm %s\n", data.Text() ); }

private:
    StrBuf    data;
};

static int intrCount = 0;
static const int maxIntr = 3;

// Replacement handler for SIGINT signals. Overrides Signaler class's
// default handler to avoid immediate exit.

static void trap_interrupt( int sig )
{
    intrCount++;
    printf( "Received SIGINT. Calling registered functions...\n" );
    signaler.Intr();
    printf( "All functions done\n\n" );
    if ( intrCount >= maxIntr )
    {
        printf( "Interrupt limit hit. Exiting...\n" );
        exit( 0 );
    }
}

static void InterruptHandler( void *p )
{
    MyClass    *m = ( MyClass * )p;
    m->Identify();

    // Don't identify this object again
    signaler.DeleteOnIntr( p );
}

int main( int argc, char **argv )
{
    signal( SIGINT, trap_interrupt );
    signaler.Catch();
}

```

```
int objCount = 5;
int nextId = 1;
for ( ; ; )
{
    int i;
    for ( i = nextId; i < nextId + objCount; i++ )
    {
        StrBuf data;

        data.Set( "Object" );
        data << i;

        MyClass *p = new MyClass;
        p->Set( &data );

        printf( "Registering %s\n", data.Text() );
        signaler.OnIntr( InterruptHandler, ( void * )p );
    }

    nextId = i;
    printf( "\n" );
    printf( "Hit ^C to fire the interrupt handler [%d to go]\n",
           maxIntr - intrCount );
    sleep( 10 );
}

exit( 0 );
}
```

**Signaler::OnIntr( SignalFunc, void \* )**

Register a function and argument to be called when an interrupt signal is received.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">Signaler</a>	
<b>Arguments</b>	<b>SignalFunc callback</b>	Pointer to a function to call on receipt of an interrupt signal.  The function must have the prototype <b>voidfunc( void *ptr )</b>
	<b>void *ptr</b>	Pointer to a data item to pass to the callback function when invoking it.
<b>Returns</b>	<b>void</b>	

**Notes**

Functions are called in the reverse order that they are registered.

**See also**

[Signaler::DeleteOnIntr\(\)](#) [Signaler::Intr\(\)](#)

## Example

```
#include <unistd.h>    // for sleep()
#include <stdhdrs.h>
#include <strbuf.h>
#include <signaler.h>

class MyClass
{
public:
    void      Set( StrPtr *d ) { data = *d; }
    const StrPtr *Get()      { return &data; }
    void      Identify()     { printf( "I'm %s\n", data.Text() ); }

private:
    StrBuf    data;
};

static void InterruptHandler( void *p )
{
    MyClass    *m = ( MyClass * )p;
    m->Identify();
}

int main( int argc, char **argv )
{
    for ( int i = 1; i <= 5; i++ )
    {
        StrBuf data;

        data.Set( "Object" );
        data << i;

        MyClass *p = new MyClass;
        p->Set( &data );

        signaler.OnIntr( InterruptHandler, ( void * )p );
    }

    printf( "Hit ^C to fire the interrupt handler\n" );
    for ( ; ; )
        sleep( 60 );

    exit( 0 );
}
```

## Signaler::Signaler() (constructor)

Constructs a new `Signaler` object.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">Signaler</a>
<b>Arguments</b>	N/A
<b>Returns</b>	N/A

### Notes

There is rarely a need for API users to construct `Signaler` objects themselves. Use the global `Signaler` variable `signaler` instead.

### See also

[Signaler::OnIntr\(\)](#) [Signaler::DeleteOnIntr\(\)](#)

## StrBuf methods

---

### StrBuf::Alloc( int )

Allocate an additional specified number of bytes to a **StrBuf**. The string pointed to by the **StrBuf**'s **buffer** is logically extended.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	<b>int len</b>	number of bytes to be allocated
<b>Returns</b>	<b>char *</b>	pointer to the first additional byte allocated

### Notes

The length of the **StrBuf** is incremented by the **len** argument.

If the memory for the **StrBuf**'s **buffer** is not large enough, enough new memory is allocated to contiguously contain the extended string. If new memory is allocated, the old memory is freed. (All **StrBuf** member functions with the potential to increase the length of a **StrBuf** manage memory this way.)

A call to [Alloc\(\)](#) might change the string pointed to by the **StrBuf**'s **buffer**; do not rely on pointer arithmetic to determine the new pointer, because the call to [Alloc\(\)](#) might have moved the **buffer** location.



**Example**

```

#include <iostream>
#include <iomanip>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sb;
    char *p;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb.Alloc( 70 ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "(int)sb.Text() prior to sb.Alloc( 70 ) returns 0x" << hex;
    cout << setw( 8 ) << setfill( '0' ) << (int)sb.Text() << dec << "\n";
    cout << "sb.Length() prior to sb.Alloc( 70 ) returns ";
    cout << sb.Length() << "\n\n";

    p = sb.Alloc( 70 ); // allocate in StrBuf

    cout << "sb.Text() after sb.Alloc( 70 ) returns (first three bytes) ";
    cout << "\"" << setw( 3 ) << sb.Text() << "\"\n";
    cout << "(int)sb.Text() after sb.Alloc( 70 ) returns 0x" << hex;
    cout << setw( 8 ) << setfill( '0' ) << (int)sb.Text() << dec << "\n";
    cout << "(int)sb.Alloc( 70 ) returned 0x" << hex;
    cout << setw( 8 ) << setfill( '0' ) << (int)p << dec << "\n";
    cout << "sb.Length() after sb.Alloc( 70 ) returns ";
    cout << sb.Length() << "\n";
}

```

Executing the preceding code produces the following output:

```

sb.Text() prior to sb.Alloc( 70 ) returns "xyz"
(int)sb.Text() prior to sb.Alloc( 70 ) returns 0x0804a9a0
sb.Length() prior to sb.Alloc( 70 ) returns 3

sb.Text() after sb.Alloc( 70 ) returns (first three bytes) "xyz"
(int)sb.Text() after sb.Alloc( 70 ) returns 0x0804a9b0
(int)sb.Alloc( 70 ) returned 0x0804a9b3
sb.Length() after sb.Alloc( 70 ) returns 73

```

## StrBuf::Append( const char \* )

Append a null-terminated string to a `StrBuf`. The string is logically appended to the string pointed to by the `StrBuf`'s `buffer`.

Virtual?	No	
Class	<a href="#">StrBuf</a>	
Arguments	<code>const char *buf</code>	pointer to the first byte of the null-terminated string
Returns	<code>void</code>	

### Notes

The `StrBuf`'s `length` is incremented by the number of bytes prior to the first null byte in the string.

If the memory for the `StrBuf`'s `buffer` is not large enough, new memory to contiguously contain the results of appending the null-terminated string is allocated. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the string.

### Example

```
int main( int argc, char **argv )
{
    char chars[] = "zy";
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb.Append( chars ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() prior to sb.Append( chars ) returns ";
    cout << sb.Length() << "\n\n";

    sb.Append( chars ); // append char * to StrBuf

    cout << "sb.Text() after sb.Append( chars ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() after sb.Append( chars ) returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb.Append( chars ) returns "xyz"
sb.Length() prior to sb.Append( chars ) returns 3

sb.Text() after sb.Append( chars ) returns "xyzy"
sb.Length() after sb.Append( chars ) returns 5
```

## StrBuf::Append( const char \*, int )

Append a string of a specified length to a `StrBuf`. The string is logically appended to the string pointed to by the `StrBuf`'s `buffer`.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	<code>const char *buf</code>	pointer to the first byte of the string
	<code>int len</code>	length of the string
<b>Returns</b>	<code>void</code>	

### Notes

Exactly `len` bytes are appended to the `StrBuf` from the string. The `length` of the `StrBuf` is incremented by the `len` argument.

If the memory for the `StrBuf`'s `buffer` is not large enough, new memory to contiguously contain the results of appending the string of specified length is allocated. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the string.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "zyx";
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb.Append( chars, 2 ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() prior to sb.Append( chars, 2 ) returns ";
    cout << sb.Length() << "\n\n";

    sb.Append( chars, 2 ); // append len bytes of char * to StrBuf

    cout << "sb.Text() after sb.Append( chars, 2 ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() after sb.Append( chars, 2 ) returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb.Append( chars, 2 ) returns "xyz"  
sb.Length() prior to sb.Append( chars, 2 ) returns 3
```

```
sb.Text() after sb.Append( chars, 2 ) returns "xyzyz"  
sb.Length() after sb.Append( chars, 2 ) returns 5
```

## StrBuf::Append( const StrPtr \* )

Append a `StrPtr` to a `StrBuf`. The argument is passed as a pointer to the `StrPtr`. The string pointed to by the `StrPtr`'s `buffer` is logically appended to the string pointed to by the `StrBuf`'s `buffer`. Arguments are commonly addresses of instances of classes derived from the `StrPtr` class, such as `StrRef` and `StrBuf`.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	<code>const StrPtr *s</code>	pointer to the <code>StrPtr</code> instance
<b>Returns</b>	<code>void</code>	

### Notes

Initialize the `StrBuf` and the `StrPtr` before calling [Append\(\)](#).

Exactly the number of bytes specified by the `length` of the `StrPtr` are appended to the `StrBuf` from the `StrPtr`. The `length` of the `StrBuf` is incremented by the `length` of the `StrPtr`.

If the memory for the `StrBuf`'s `buffer` is not large enough, new memory to contiguously contain the results of appending the `StrPtr` is allocated. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the `StrPtr`.

**Example**

```

#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "zy" );
    StrPtr *sp = &sr;
    StrBuf sba;
    StrBuf sbb;

    sba.Set( "xyz" );
    sbb.Set( "xyz" );

    cout << "sba.Text() after sba.Set( \"xyz\" ) returns ";
    cout << "\"" << sba.Text() << "\"\n";
    cout << "sba.Length() after sba.Set( \"xyz\" ) returns ";
    cout << sba.Length() << "\n";
    cout << "sbb.Text() after sbb.Set( \"xyz\" ) returns ";
    cout << "\"" << sbb.Text() << "\"\n";
    cout << "sbb.Length() after sbb.Set( \"xyz\" ) returns ";
    cout << sbb.Length() << "\n\n";

    sba.Append( sp ); // append StrPtr * to StrBuf

    cout << "sba.Text() after sba.Append( sp ) returns ";
    cout << "\"" << sba.Text() << "\"\n";
    cout << "sba.Length() after sba.Append( sp ) returns ";
    cout << sba.Length() << "\n\n";

    sbb.Append( &sr ); // append &StrRef to StrBuf

    cout << "sbb.Text() after sbb.Append( &sr ) returns ";
    cout << "\"" << sbb.Text() << "\"\n";
    cout << "sbb.Length() after sbb.Append( &sr ) returns ";
    cout << sbb.Length() << "\n\n";

    sba.Append( &sbb ); // append &StrBuf to StrBuf

    cout << "sba.Text() after sba.Append( &sbb ) returns ";
    cout << "\"" << sba.Text() << "\"\n";
    cout << "sba.Length() after sba.Append( &sbb ) returns ";
    cout << sba.Length() << "\n";
}

```

Executing the preceding code produces the following output:

```
sba.Text() after sba.Set( "xyz" ) returns "xyz"
sba.Length() after sba.Set( "xyz" ) returns 3
sbb.Text() after sbb.Set( "xyz" ) returns "xyz"
sbb.Length() after sbb.Set( "xyz" ) returns 3

sba.Text() after sba.Append( sp ) returns "xyzzy"
sba.Length() after sba.Append( sp ) returns 5
sbb.Text() after sbb.Append( &sr ) returns "xyzzy"
sbb.Length() after sbb.Append( &sr ) returns 5
sba.Text() after sba.Append( &sbb ) returns "xyzzyxyzzy"
sba.Length() after sba.Append( &sbb ) returns 10
```

## StrBuf::Clear()

Clear the length member of a `StrBuf`.

Virtual?	No
Class	<a href="#">StrBuf</a>
Arguments	None
Returns	void

### Notes

Only the `length` member of the `StrBuf` is zeroed.

To set the `buffer` member to a zero-length string, call [Terminate\(\)](#) after calling [Clear\(\)](#).

### See also

[StrBuf::Terminate\(\)](#)

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "Prior to sb.Clear() and sb.Terminate():\n";
    cout << "  sb.Length() returns " << sb.Length() << "\n";
    cout << "  sb.Text() returns \"" << sb.Text() << "\"\n\n";

    sb.Clear(); // zero out the length

    cout << "After sb.Clear() but prior to sb.Terminate():\n";
    cout << "  sb.Length() returns " << sb.Length() << "\n";
    cout << "  sb.Text() returns \"" << sb.Text() << "\"\n\n";

    sb.Terminate();

    cout << "After sb.Clear() and sb.Terminate():\n";
    cout << "  sb.Length() returns " << sb.Length() << "\n";
    cout << "  sb.Text() returns \"" << sb.Text() << "\"\n";
}
```



Executing the preceding code produces the following output:

```
Prior to sb.Clear() and sb.Terminate():  
  sb.Length() returns 3  
  sb.Text() returns "xyz"  
  
After sb.Clear() but prior to sb.Terminate():  
  sb.Length() returns 0  
  sb.Text() returns "xyz"  
  
After sb.Clear() and sb.Terminate():  
  sb.Length() returns 0  
  sb.Text() returns ""
```

## StrBuf::StrBuf() (Constructor)

Construct a StrBuf.

Virtual?	No
Class	<a href="#">StrBuf</a>
Arguments	None

### Notes

The StrBuf constructor initializes the StrBuf to contain a zero-length null buffer.

### Example

```
int main( int argc, char **argv )
{
    StrBuf sb; // constructor called

    cout << "sb.Text() returns \"" << sb.Text() << "\"\n";
    cout << "sb.Length() returns " << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() returns ""
sb.Length() returns 0
```

## StrBuf::StrBuf( const StrBuf & ) (Copy Constructor)

Construct a copy of a StrBuf.

Virtual?	No	
Class	<a href="#">StrBuf</a>	
Arguments	const StrBuf &s	(implied) reference of the StrBuf from which copying occurs

### Notes

The StrBuf copy constructor creates a copy of a StrBuf. The StrBuf from which copying occurs must be initialized before calling the copy constructor.

The StrBuf copy constructor initializes the new StrBuf to contain a zero-length null buffer, and sets the contents of the new StrBuf using the contents of the original StrBuf. Any memory allocated for the buffer of the copy is separate from the memory for the buffer of the original StrBuf.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

void called( StrBuf csb )
{
    csb << "zy";

    cout << "called() csb.Text() returns \"" << csb.Text() << "\"\n";
}

int main( int argc, char **argv )
{
    StrBuf sb;
    sb.Set( "xyz" );
    called( sb ); // copy constructor called
    cout << "main() sb.Text() returns \"" << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
called() csb.Text() returns "xyzy"
main() sb.Text() returns "xyz"
```

## StrBuf::~StrBuf() (Destructor)

Destroy a StrBuf.

<b>Virtual?</b>	No
<b>Class</b>	<a href="#">StrBuf</a>
<b>Arguments</b>	None
<b>Returns</b>	N/A

### Notes

The StrBuf destructor destroys a StrBuf.

If the `buffer` points to allocated memory other than `nullStrBuf`, the allocated memory is freed.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf *psb;
    psb = new StrBuf;
    psb->Set( "xyz" );
    cout << psb- → Text() returns \" << psb->Text() << "\\n";
    delete psb; // destructor called and allocated memory freed
}
```

Executing the preceding code produces the following output:

```
psb->Text() returns "xyz"
```

## StrBuf::Extend( char )

Extend a `StrBuf` by one byte. The string pointed to by the `StrBuf`'s `buffer` is logically extended.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	<code>char c</code>	the byte copied to the extended string
<b>Returns</b>	<code>void</code>	

### Notes

One byte is copied to the extended `StrBuf`. The `length` of the `StrBuf` is incremented by one.

[Extend\(\)](#) does not null-terminate the extended string pointed to by the `StrBuf`'s `buffer`. To ensure that the extended string is null-terminated, call [Terminate\(\)](#) after calling [Extend\(\)](#).

If the memory for the `StrBuf`'s `buffer` is not large enough, enough new memory is allocated to contiguously contain the extended string. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the byte.

### See also

[StrBuf::Terminate\(\)](#)

## Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sb;

    sb.Set( "xy" );

    cout << "sb.Text() prior to sb.Extend( 'z' ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() prior to sb.Extend( 'z' ) returns ";
    cout << sb.Length() << "\n\n";

    sb.Extend( 'z' ); // extend StrBuf from char
    sb.Terminate();

    cout << "sb.Text() after sb.Extend( 'z' ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() after sb.Extend( 'z' ) returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb.Extend( 'z' ) returns "xy"
sb.Length() prior to sb.Extend( 'z' ) returns 2

sb.Text() after sb.Extend( 'z' ) returns "xyz"
sb.Length() after sb.Extend( 'z' ) returns 3
```

## StrBuf::Extend( const char \*, int )

Extend a `StrBuf` by a string of a specified length. The string pointed to by the `StrBuf`'s `buffer` is logically extended.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	<code>const char *buf</code>	pointer to the first byte of the string
	<code>int len</code>	length of the string
<b>Returns</b>	<code>void</code>	

### Notes

Exactly `len` bytes are copied from the string to the extended `StrBuf`. The length of the `StrBuf` is incremented by `len` bytes.

[Extend\(\)](#) does not null-terminate the extended string pointed to by the `StrBuf`'s `buffer`. To ensure that the extended string is null-terminated, call [Terminate\(\)](#) after calling [Extend\(\)](#).

If the memory for the `StrBuf`'s `buffer` is not large enough, enough new memory is allocated to contiguously contain the extended string. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the string.

### See also

[StrBuf::Terminate\(\)](#)

## Example

```
int main( int argc, char **argv )
{
    char chars[] = "zyx";
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb.Extend( chars, 2 ) returns ";
    cout << "\"" << sb.Text() << "\\n";
    cout << "sb.Length() prior to sb.Extend( chars, 2 ) returns ";
    cout << sb.Length() << "\\n\\n";

    sb.Extend( chars, 2 ); // extend StrBuf from len bytes of char *
    sb.Terminate();

    cout << "sb.Text() after sb.Extend( chars, 2 ) returns ";
    cout << "\"" << sb.Text() << "\\n";
    cout << "sb.Length() after sb.Extend( chars, 2 ) returns ";
    cout << sb.Length() << "\\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb.Extend( chars, 2 ) returns "xyz"
sb.Length() prior to sb.Extend( chars, 2 ) returns 3
sb.Text() after sb.Extend( chars, 2 ) returns "xyzy"
sb.Length() after sb.Extend( chars, 2 ) returns 5
```



## StrBuf::operator =( const char \* )

Assign a StrBuf from a null-terminated string.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	const char *buf	(implied) pointer to the first byte of the null-terminated string
<b>Returns</b>	void	

### Notes

Initialize the StrBuf before the assignment.

The length is set to the number of bytes prior to the first null byte in the string.

Any memory allocated for the StrBuf's buffer is separate from the memory for the string.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyz";
    StrBuf sb;

    sb = chars;    // assign StrBuf from char *

    cout << "chars[] = \"" << chars << "\"\n";
    cout << "sb.Text() returns \"" << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyz"
sb.Text() returns "xyz"
```

## StrBuf::operator =( const StrBuf & )

Assign a `StrBuf` from another `StrBuf`.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	<code>const StrBuf &amp;buf</code>	(implied) reference of the <code>StrBuf</code> from which assignment occurs
<b>Returns</b>	<code>void</code>	

### Notes

Initialize both `StrBuf`s before the assignment.

Any memory allocated for the assigned `StrBuf`'s `buffer` is separate from the memory for the `StrBuf`'s `buffer` from which assignment occurs.

Do not assign a `StrBuf` to itself.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sba;
    StrBuf sbb;

    sba.Set( "xyz" );

    sbb = sba;    // assign StrBuf to StrBuf

    cout << "sba.Text() returns \"" << sba.Text() << "\"\n";
    cout << "sbb.Text() returns \"" << sbb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sba.Text() returns "xyz"
sbb.Text() returns "xyz"
```

## StrBuf::operator =( const StrPtr & )

Assign a StrBuf from a StrPtr.

Virtual?	No	
Class	<a href="#">StrBuf</a>	
Arguments	const StrPtr &s	(implied) reference of the StrPtr instance
Returns	void	

### Notes

Initialize the StrBuf and the StrPtr before assignment.

Any memory allocated for the StrBuf's **buffer** is separate from the memory for the StrPtr's **buffer**.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "xyz" );
    StrPtr *sp = &sr;
    StrBuf sb;

    sb = *sp; // assign StrBuf from StrPtr

    cout << sp->Text() returns \ " << sp->Text() << "\n";
    cout << "sb.Text() returns \ " << sb.Text() << "\n";
}
```

Executing the preceding code produces the following output:

```
sp->Text() returns "xyz"
sb.Text() returns "xyz"
```

## StrBuf::operator =( const StrRef & )

Assign a `StrBuf` from a `StrRef`.

Virtual?	No
Class	<a href="#">StrBuf</a>
Arguments	<code>const StrRef &amp;s</code> (implied) reference of the <code>StrRef</code> instance
Returns	<code>void</code>

### Notes

Initialize the `StrBuf` and `StrRef` before assignment.

Any memory allocated for the `StrBuf`'s `buffer` is separate from that of the `StrRef`'s `buffer`.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "xyz" );
    StrBuf sb;

    sb = sr; // assign StrBuf from StrRef

    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
    cout << "sb.Text() returns \"" << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sr.Text() returns "xyz"
sb.Text() returns "xyz"
```

## StrBuf::operator <<( const char \* )

Append a null-terminated string to a `StrBuf`. The string is logically appended to the string pointed to by the `StrBuf`'s `buffer`.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	<code>const char *s</code>	(implied) pointer to the first byte of the null-terminated string
<b>Returns</b>	<code>StrBuf &amp;</code>	reference of the <code>StrBuf</code>

### Notes

The `StrBuf`'s `length` is incremented by the number of bytes prior to the first null byte in the string.

If the memory for the `StrBuf`'s `buffer` is not large enough, new contiguous memory is allocated to contain the results of appending the null-terminated string. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the string.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "zy";
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb << chars returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() prior to sb << chars returns ";
    cout << sb.Length() << "\n\n";

    sb << chars; // append char * to StrBuf

    cout << "sb.Text() after sb << chars returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() after sb << chars returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb << chars returns "xyz"  
sb.Length() prior to sb << chars returns 3  
  
sb.Text() after sb << chars returns "xyzyz"  
sb.Length() after sb << chars returns 5
```

## StrBuf::operator <<( int )

Append a formatted integer to a `StrBuf`. The formatted integer is logically appended to the string pointed to by the `StrBuf`'s `buffer`.

Virtual?	No	
Class	<a href="#">StrBuf</a>	
Arguments	<code>int v</code>	(implied) integer
Returns	<code>StrBuf &amp;</code>	reference of the <code>StrBuf</code>

### Notes

The integer is formatted with the logical equivalent of `sprintf( buf, "%d", v )`.

The `length` is incremented by the number of bytes of the formatted integer.

If the memory for the `StrBuf`'s `buffer` is not large enough, new contiguous memory is allocated to contain the results of appending the formatted integer. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the formatted integer.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sb;
    int i;

    sb.Set( "xyz" );
    i = 73;

    cout << "sb.Text() prior to sb << i returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() prior to sb << i returns ";
    cout << sb.Length() << "\n\n";

    sb << i; // append (formatted) int to StrBuf

    cout << "sb.Text() after sb << i returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() after sb << i returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb << i returns "xyz"  
sb.Length() prior to sb << i returns 3
```

```
sb.Text() after sb << i returns "xyz73"  
sb.Length() after sb << i returns 5
```



## StrBuf::operator <<( const StrPtr \* )

Append a StrPtr to a StrBuf. The string pointed to by the StrPtr's `buffer` is logically appended to the string pointed to by the StrBuf's `buffer`.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	<code>const StrPtr *s</code>	(implied) pointer to the StrPtr instance
<b>Returns</b>	<code>StrBuf &amp;</code>	reference of the StrBuf

### Notes

Exactly the number of bytes specified by the StrPtr's `length` are appended to the StrBuf. The StrBuf's `length` is incremented by the StrPtr's `length`.

If the memory for the StrBuf's `buffer` is not large enough, new contiguous memory is allocated to contain the results of appending the StrPtr. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the StrPtr.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "zy" );
    StrPtr *sp = &sr;
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb << sp returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() prior to sb << sp returns ";
    cout << sb.Length() << "\n\n";

    sb << sp;    // append StrPtr * to StrBuf

    cout << "sb.Text() after sb << sp returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() after sb << sp returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb << sp returns "xyz"  
sb.Length() prior to sb << sp returns 3  
  
sb.Text() after sb << sp returns "xyzzy"  
sb.Length() after sb << sp returns 5
```

## StrBuf::operator <<( const StrPtr & )

Append a `StrPtr` to a `StrBuf`. The argument is passed as a reference of the `StrPtr`. The string pointed to by the `StrPtr`'s `buffer` is logically appended to the string pointed to by the `StrBuf`'s `buffer`.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	<code>const StrPtr &amp;s</code>	(implied) reference of the <code>StrPtr</code> instance
<b>Returns</b>	<code>StrBuf &amp;</code>	reference of the <code>StrBuf</code>

### Notes

Arguments are typically instances of classes derived from the `StrPtr` class, such as `StrRef` and `StrBuf`.

Exactly the number of bytes specified by the `length` of the `StrPtr` are appended to the `StrBuf` from the `StrPtr`. The `length` of the `StrBuf` is incremented by the `length` of the `StrPtr`.

If the memory for the `StrBuf`'s `buffer` is not large enough, new contiguous memory is allocated to contain the results of appending the `StrPtr`. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the `StrPtr`.

**Example**

```

#include <iostream>

#include <string.h>
#include <stringbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "zy" );
    StrPtr *sp = &sr;
    StrBuf sba;
    StrBuf sbb;

    sba.Set( "xyzy" );
    sbb.Set( "xyz" );

    cout << "sba.Text() after sba.Set( \"xyzy\" ) returns ";
    cout << "\"" << sba.Text() << "\"\n";
    cout << "sba.Length() after sba.Set( \"xyzy\" ) returns ";
    cout << sba.Length() << "\n";
    cout << "sbb.Text() after sbb.Set( \"xyz\" ) returns ";
    cout << "\"" << sbb.Text() << "\"\n";
    cout << "sbb.Length() after sbb.Set( \"xyz\" ) returns ";
    cout << sbb.Length() << "\n";

    sbb << sr;    // append StrRef to StrBuf

    cout << "sbb.Text() after sbb << sr returns ";
    cout << "\"" << sbb.Text() << "\"\n";
    cout << "sbb.Length() after sbb << sr returns ";
    cout << sbb.Length() << "\n";

    sba << sbb;    // append StrBuf to StrBuf

    cout << "sba.Text() after sba << sbb returns ";
    cout << "\"" << sba.Text() << "\"\n";
    cout << "sba.Length() after sba << sbb returns ";
    cout << sba.Length() << "\n";
}

```

Executing the preceding code produces the following output:

```

sba.Text() after sba.Set( "xyzy" ) returns "xyzy"
sba.Length() after sba.Set( "xyzy" ) returns 5
sbb.Text() after sbb.Set( "xyz" ) returns "xyz"
sbb.Length() after sbb.Set( "xyz" ) returns 3
sbb.Text() after sbb << sr returns "xyzy"
sbb.Length() after sbb << sr returns 5
sba.Text() after sba << sbb returns "xyzyxyzy"
sba.Length() after sba << sbb returns 10

```

## StrBuf::Set( const char \* )

Set a StrBuf from a null-terminated string.

Virtual?	No	
Class	<a href="#">StrBuf</a>	
Arguments	const char *buf	pointer to the first byte of the null-terminated string
Returns	void	

### Notes

Initialize the StrBuf before calling [Set\(\)](#).

The length of the StrBuf is set to the number of bytes prior to the first null byte in the string.

Any memory allocated for the StrBuf's buffer is separate from the memory for the string.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "string";
    StrBuf sb;

    sb.Set( chars ); // set StrBuf from char *

    cout << "chars[] = \"" << chars << "\"\n";
    cout << "sb.Text() returns \"" << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "string"
sb.Text() returns "string"
```

## StrBuf::Set( const char \*, int )

Set a StrBuf from a string of a specified length.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrBuf</a>	
<b>Arguments</b>	const char *buf	pointer to the first byte of the string
	int len	length of the string
<b>Returns</b>	void	

### Notes

Initialize the StrBuf before calling [Set\(\)](#).

Exactly len bytes are copied from the string to the StrBuf. The length of the StrBuf is set to the len argument.

Any memory allocated for the StrBuf's buffer is separate from the memory for the string.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyzy";
    StrBuf sb;

    sb.Set( chars, 3 ); // set StrBuf from len bytes of char *

    cout << "chars[] = \"\" << chars << "\"\n";
    cout << "sb.Text() returns \"\" << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyzy"
sb.Text() returns "xyz"
```

## StrBuf::Set( const StrPtr \* )

Set a StrBuf from a pointer to a StrPtr.

Virtual?	No	
Class	<a href="#">StrBuf</a>	
Arguments	const StrPtr *s	pointer to the StrPtr instance
Returns	void	

### Notes

Initialize the StrBuf and the StrPtr before calling [Set\(\)](#).

Any memory allocated for the StrBuf's **buffer** is separate from the memory for the StrPtr's **buffer**.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "xyz" );
    StrPtr *sp = &sr;
    StrBuf sb;

    sb.Set( sp ); // set StrBuf from StrPtr *

    cout << sp->Text() returns \ " << sp->Text() << "\n";
    cout << "sb.Text() returns \ " << sb.Text() << "\n";
}
```

Executing the preceding code produces the following output:

```
sp->Text() returns "xyz"
sb.Text() returns "xyz"
```

## StrBuf::Set( const StrPtr & )

Set a `StrBuf` from a reference of a `StrPtr`. Arguments are commonly instances of classes derived from the `StrPtr` class, such as `StrRef` and `StrBuf`.

Virtual?	No
Class	<a href="#">StrBuf</a>
Arguments	<code>const StrPtr &amp;s</code> reference of the <code>StrPtr</code> instance
Returns	<code>void</code>

### Notes

Initialize the `StrBuf` and the `StrPtr` before calling [Set\(\)](#).

Any memory allocated for the `StrBuf`'s `buffer` is separate from the memory for the `StrPtr`'s `buffer`.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr;
    StrBuf sbs;
    StrBuf sbt;

    sr.Set( "xyz" );
    sbt.Set( sr );    // set StrBuf from StrRef

    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
    cout << "sbt.Text() returns \"" << sbt.Text() << "\"\n\n";

    sbs.Set( "abc" );
    sbt.Set( sbs );    // set StrBuf from StrBuf

    cout << "sbs.Text() returns \"" << sbs.Text() << "\"\n";
    cout << "sbt.Text() returns \"" << sbt.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:



```
sr.Text() returns "xyz"  
sbt.Text() returns "xyz"  
  
sbs.Text() returns "abc"  
sbt.Text() returns "abc"
```

## StrBuf::StringInit()

Initialize a StrBuf.

Virtual?	No
Class	<a href="#">StrBuf</a>
Arguments	None
Returns	void

### Notes

[StringInit\(\)](#) initializes the StrBuf to contain a zero-length null buffer.

Normally when a StrBuf is created, it is initialized using the StrBuf constructor. However, there may be specialized cases where memory has already been allocated for a StrBuf instance, but the memory was not allocated through the normal mechanisms that would result in the StrBuf constructor initializing the instance. For these specialized cases, [StringInit\(\)](#) is appropriate for initializing a StrBuf instance.

After a StrBuf has been used, calling [StringInit\(\)](#) for the instance can result in a memory leak. Specifically, once the `buffer` member has been pointed to memory other than `nullStrBuf`, calling [StringInit\(\)](#) for the instance will abandon the memory.

In most cases, it is preferable to use an alternative such as one of the following:

```
sb1 = StrRef::Null();

sb2.Clear();
sb2.Terminate();

sb3.Set( "" );

sb4 = "";
```

### See also

[StrBuf::Clear\(\)](#) [StrBuf::Set\(\)](#) [StrBuf::Terminate\(\)](#) [StrBuf::operator =\( char \\* \)](#) [StrRef::Null\(\)](#)

**Example**

```

#include <iostream>
#include <errno.h>

#include <stdhdrs.h>
#include <strbuf.h>

#define NSTRBUFS    5
#define CHUNKSIZE  1024
#define STRBUFSIZE  sizeof( StrBuf )

int main( int argc, char **argv )
{
    char chunk[ CHUNKSIZE ];
    int chunkFree = CHUNKSIZE;
    char *pchunkStart = &chunk[ 0 ];
    char *pchunk;

    int iStrBuf;

    // Initialize the StrBufs in the chunk.

    for ( iStrBuf = 0, pchunk = pchunkStart;
          iStrBuf < NSTRBUFS;
          iStrBuf, pchunk += STRBUFSIZE )
    {
        // Ensure that there's enough free left in the chunk for a StrBuf.
        if ( (chunkFree -= STRBUFSIZE) &lt; 0)
        {
            cout &lt;&lt; "Not enough free left in the chunk!\n";
            return ENOMEM;
        }

        // Initialize and set the value of the StrBuf.

        ((StrBuf *)pchunk)-&gt;StringInit();
        *(StrBuf *)pchunk &lt;&lt; iStrBuf + 73;
    }

    // Print the StrBufs. Do this in a separate loop so as to provide
    // some evidence that the above loop didn't corrupt adjacent StrBufs.
    for ( iStrBuf = 0, pchunk = pchunkStart;
          iStrBuf &lt; NSTRBUFS;
          iStrBuf, pchunk += STRBUFSIZE )
    {
        cout &lt;&lt; "StrBuf " &lt;&lt; iStrBuf + 1 &lt;&lt; " contains \";
        cout &lt;&lt; ((StrBuf *)pchunk)-&gt;Text() &lt;&lt; "\"\n";
    }
}

```

Executing the preceding code produces the following output:

```
StrBuf 1 contains "73"  
StrBuf 2 contains "74"  
StrBuf 3 contains "75"  
StrBuf 4 contains "76"  
StrBuf 5 contains "77"
```

## StrBuf::Terminate()

Null-terminate the string pointed to by the `buffer` member of a `StrBuf`. The null byte is placed in the buffer at the location indicated by the `length` member.

Virtual?	No
Class	<a href="#">StrBuf</a>
Arguments	None
Returns	void

### Notes

Initialize the `StrBuf` before calling [Terminate\(\)](#).

The `length` member of the `StrBuf` is effectively unchanged by [Terminate\(\)](#).

### Example

[Terminate\(\)](#) is defined in `strbuf.h` as follows:

```
void Terminate()
{
    Extend( 0 ); --length;
}
```

[Terminate\(\)](#) null-terminates the string by calling `Extend( 0 )`, which also increments the `length` member; the `length` is then decremented within [Terminate\(\)](#), leaving it unchanged.

### See also

[StrBuf::StringInit\(\)](#)

**Example**

```

#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sb;

    sb.Set( "xyzyz" );

    cout << "Prior to sb.SetLength( 3 ) and sb.Terminate():\n";
    cout << "  sb.Length() returns " << sb.Length() << "\n";
    cout << "  sb.Text() returns \"" << sb.Text() << "\"\n\n";

    sb.SetLength( 3 );

    cout << "After sb.SetLength( 3 ) but prior to sb.Terminate():\n";
    cout << "  sb.Length() returns " << sb.Length() << "\n";
    cout << "  sb.Text() returns \"" << sb.Text() << "\"\n\n";

    sb.Terminate();    // null-terminate the string at length

    cout << "After sb.SetLength( 3 ) and sb.Terminate():\n";
    cout << "  sb.Length() returns " << sb.Length() << "\n";
    cout << "  sb.Text() returns \"" << sb.Text() << "\"\n";
}

```

Executing the preceding code produces the following output:

```

Prior to sb.SetLength( 3 ) and sb.Terminate():
  sb.Length() returns 5
  sb.Text() returns "xyzyz"

After sb.SetLength( 3 ) but prior to sb.Terminate():
  sb.Length() returns 3
  sb.Text() returns "xyzyz"

After sb.SetLength( 3 ) and sb.Terminate():
  sb.Length() returns 3
  sb.Text() returns "xyz"

```

## StrDict methods

### StrDict::GetVar( const StrPtr & )

Return the value of the specified variable, or **NULL** if not defined.

Virtual?	No	
Class	<a href="#">StrDict</a>	
Arguments	const StrPtr &var	the name of the variable to look up
Returns	StrPtr *	the value, or <b>NULL</b> if not defined

### Notes

For the most part, all of the following methods are equivalent:

- `StrDict::GetVar( const StrPtr & )`
- `StrDict::GetVar( const char * )`
- `StrDict::GetVar( const char *, Error * )`
- `StrDict::GetVar( const StrPtr &, int )`
- `StrDict::GetVar( const StrPtr &, int, int )`
- `StrDict::GetVar( int, StrPtr &, StrPtr & )`

The `var` argument must specify the name of a variable in the `StrDict` that you're trying to look up. In some instances, variables in a `StrDict` are named according to the convention **FOOx** or **FOOx,y** - one example is the tagged output of **p4 filelog**. Calling `GetVar()` with these numbers as arguments saves you the work of manually constructing the variable name by using `itoa()` and `Append()`.

The version of `GetVar()` that returns an `int` is useful for iterating through a `StrDict`; the `int` argument is an index into the `StrDict`, and the two `StrPtr` arguments are set to contain the variable and value found at that index, if any. This method returns zero if there was no variable at the specified index.

### Example

The implementation of `ClientUser::OutputStat()` in `clientuser.cc` provides a good source example:

```

void ClientUser::OutputStat( StrDict *varList )
{
    int i;
    StrBuf msg;
    StrRef var, val;

    // Dump out the variables, using the GetVar( x ) interface.
    // Don't display the function, which is only relevant to rpc.
    for ( i = 0; varList->GetVar( i, var, val ); i++ )
    {
        if ( var == "func" ) continue;

        // otherAction and otherOpen go at level 2, as per 99.1 + earlier
        msg.Clear();
        msg << var << " " << val;
        char level = strcmp( var.Text(), "other", 5 ) ? '1' : '2';
        OutputInfo( level, msg.Text() );
    }

    // blank line
    OutputInfo( '0', "" );
}

```

An example of output:

```

% p4 -Ztag filelog file.c

... depotFile //depot/depot/source/file.c
... rev0 3
... change0 1949
... action0 integrate
... type0 text
... time0 1017363022
... user0 testuser
... client0 testuser-luey
... desc0 <enter description here>
... how0,0 ignored
... file0,0 //depot/depot/source/old.c
... srev0,0 #1
... erev0,0 #2
... how0,1 ignored

...

```



## StrDict::GetVar( const char \* )

Return the value of the specified variable, or **NULL** if not defined.

Virtual?	No	
Class	<a href="#">StrDict</a>	
Arguments	const char *var	the name of the variable to look up
Returns	StrPtr *	the value, or <b>NULL</b> if not defined

### Notes

For the most part, all of the [GetVar\(\)](#) methods are equivalent.

For details, see [StrDict::GetVar\( const StrPtr & \)](#)

## StrDict::GetVar( const char \*, Error \* )

Return the value of the specified variable, or **NULL** if not defined.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrDict</a>	
<b>Arguments</b>	<code>const char *var</code>	the name of the variable to look up
	<code>Error *e</code>	an error message indicating that the required parameter <code>var</code> was not set
<b>Returns</b>	<code>StrPtr *</code>	the value, or <b>NULL</b> if not defined

### Notes

For the most part, all of the [GetVar\(\)](#) methods are equivalent.

For details, see [StrDict::GetVar\( const StrPtr & \)](#)

**StrDict::GetVar( const StrPtr &, int )**

Return the value of the specified variable, or **NULL** if not defined.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrDict</a>	
<b>Arguments</b>	const StrPtr &var	the name of the variable to look up
	int x	appended to the variable's name
<b>Returns</b>	StrPtr *	the value, or <b>NULL</b> if not defined

**Notes**

For the most part, all of the [GetVar\(\)](#) methods are equivalent.

For details, see [StrDict::GetVar\( const StrPtr & \)](#)

## StrDict::GetVar( const StrPtr &, int, int )

Return the value of the specified variable, or **NULL** if not defined.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrDict</a>	
<b>Arguments</b>	<code>const StrPtr &amp;var</code>	the name of the variable to look up
	<code>int x</code>	appended to the variable's name
	<code>int y</code>	appended to the variable's name
<b>Returns</b>	<code>StrPtr *</code>	the value, or <b>NULL</b> if not defined

### Notes

For the most part, all of the [GetVar\(\)](#) methods are equivalent.

For details, see [StrDict::GetVar\( const StrPtr & \)](#)

**StrDict::GetVar( int, StrPtr &, StrPtr & )**

Return the value of the specified variable, or **NULL** if not defined.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrDict</a>	
<b>Arguments</b>	<b>int i</b>	the index of a variable in the <b>StrDict</b>
	<b>StrPtr &amp;var</b>	the name of the variable at that index, if any
	<b>StrPtr &amp;val</b>	the value found at that index, if any
<b>Returns</b>	<b>int</b>	the value, or zero if no variable found

**Notes**

This method is typically used when iterating through a **StrDict**.

For the most part, all of the [GetVar\(\)](#) methods are equivalent.

For details, see [StrDict::GetVar\( const StrPtr & \)](#)

## StrDict::Load( FILE \* )

Unmarshals the `StrDict` from a file.

Virtual?	No	
Class	<a href="#">StrDict</a>	
Arguments	FILE *i	the file to load from
Returns	int	always equals 1

### Notes

[Load\(\)](#) loads a `StrDict` from a file previously created by [Save\(\)](#).

### Example

The following example "loads" a `StrDict` by reading it from `stdin`.

```
MyStrDict sd;
ClientUser ui;

sd.Load( stdin );
ui.OutputStat( &sd );
```

Given a marshaled `StrDict` on `stdin`, the code produces the following output:

```
> cat marshaled.strdict

depotFile=//depot/file.c
clientFile=c:\test\depot\file.c
headAction=edit
headType=text
headTime=1020067607
headRev=4
headChange=2042
headModTime 1020067484
func=client-FstatInfo

> a.out < marshaled.strdict

... depotFile //depot/file.c
... clientFile clientFile=c:\test\depot\file.c
... headAction edit
... headType text
... headTime 1020067607
... headRev 4
... headChange 2042
... headModTime 1020067484
```

## StrDict::Save( FILE \* )

Marshals the `StrDict` into a text file.

Virtual?	No	
Class	<a href="#">StrDict</a>	
Arguments	FILE *out	the file to save to
Returns	int	always equals 1

### Notes

[Save\(\)](#) stores the `StrDict` in a marshaled form to a text file, which can be recovered by using [Load\(\)](#).

### Example

The following example "saves" a `StrDict` by writing it to `stdout`.

```
void MyClientUser::OutputStat( StrDict *varList )
{
    varList->Save( stdout );
}
```

Executing the preceding code produces the following output:

```
> a.out fstat //depot/file.c

depotFile=//depot/file.c
clientFile=c:\test\depot\file.c
headAction=edit
headType=text
headTime=1020067607
headRev=4
headChange=2042
headModTime=1020067484
func=client-FstatInfo
```

## StrDict::SetArgv( int, char \*const \* )

Set a list of values, such as the arguments to a Perforce command.

Virtual?	No	
Class	<a href="#">StrDict</a>	
Arguments	int argc	the number of variables (arguments)
	char *const *argv	the variables (arguments) themselves
Returns	void	

### Notes

[SetArgv\(\)](#) is typically used when setting command arguments in `ClientApi`.

### Example

`p4api.cc` provides an example of using [SetArgv\(\)](#) to set arguments.

```
int main( int argc, char **argv )
{
    ClientUser ui;
    ClientApi client;
    Error e;

    // Any special protocol mods
    // client.SetProtocol( "tag", "" );

    // Connect to server
    client.Init( &e );

    // Run the command "argv[1] argv[2...]"
    client.SetArgv( argc - 2, argv + 2 );
    client.Run( argv[1], &ui );

    // Close connection
    client.Final( &e );

    return 0;
}
```



## StrNum methods

### StrNum::StrNum( int ) (constructor)

Create a `StrNum`, either unset or with a value.

Virtual?	No	
Class	<a href="#">StrNum</a>	
Arguments	<code>int v</code>	the number to store (optional)
Returns	<code>StrNum</code>	

### Notes

A `StrNum` always stores numbers using base ten.

To create a `StrNum` without a value, call [StrNum\(\)](#) without an argument.

### Example

The following example creates a `StrNum` and displays it:

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrNum sn = StrNum( 1666 );
    cout << "sn.Text() returns \"" << sn.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sn.Text() returns "1666"
```

## StrNum::Set( int )

Set a StrNum's value.

Virtual?	No	
Class	<a href="#">StrNum</a>	
Arguments	int v	the number to store
Returns	void	

### Notes

A StrNum always stores numbers using base ten.

### Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrNum sn;
    sn.Set ( 1666 );
    cout << "sn.Text() returns \"" << sn.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sn.Text() returns "1666"
```

## StrOps methods

### StrOps::Caps( StrBuf & )

Convert the first character in a string (in place) to uppercase.

Virtual?	No	
Class	<a href="#">StrOps</a>	
Arguments	StrBuf &o	the string to capitalize
Returns	void	

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>
#include <strops.h>

int main( int argc, char **argv )
{
    StrBuf sb;

    sb.Set( "xyzyz" );
    printf( "Before: %s\n", sb.Text() );

    StrOps::Caps( sb );
    printf( "After: %s\n", sb.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
Before: xyzyz
After: Xyzyz
```

## StrOps::Dump( const StrPtr & )

Pretty-print a string to stdout

Virtual?	No	
Class	<a href="#">StrOps</a>	
Arguments	StrPtr &o	the string to dump
Returns	void	

### Notes

Unprintable characters are displayed as hexadecimal ASCII values, surrounded by greater-than/less-than characters.

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>
#include <strops.h>

int main( int argc, char **argv )
{
    StrBuf sb;
    sb.Set( "\tXyzzy" );

    StrOps::Dump( sb );

    return 0;
}
```

Executing the preceding code produces the following output:

```
<09>Xyzzy
```

## StrOps::Expand( StrBuf &, StrPtr &, StrDict & )

Expand “`%var%`” strings into corresponding “`val`” strings from a `StrDict`.

Virtual?	No	
Class	<a href="#">StrOps</a>	
Arguments	StrBuf &o	the output string
	StrPtr &s	the input string
	StrDict &d	the var/value pairs to look up
Returns	void	

### Notes

This function provides a way to quickly expand variables from a `StrDict` into a `StrBuf`.

### Example

This small program demonstrates the [Expand\(\)](#) method in an [OutputStat\(\)](#) implementation:

```
void MyClientUser::OutputStat( StrDict *varList )
{
    StrBuf s = StrBuf();
    s.Set( "File: %depotFile% Rev: %rev%" );
    StrBuf o = StrBuf();
    StrOps::Expand( o, s, *varList );
    StrOps::Dump( o );
}

int main( int argc, char **argv )
{
    ClientApi client;
    MyClientUser ui;
    Error e;

    client.SetProtocol( "tag", "" );
    client.Init( &e );
    client.SetArgv( 1, ++argv );
    client.Run( "files", &ui );
    return client.Final( &e );
}
```

Executing the preceding code produces the following output:

```
% a.out *
File: //depot/src/file1.c Rev: 4
File: //depot/src/file2.c Rev: 2
```

## StrOps::Expand2( StrBuf &, StrPtr &, StrDict & )

Expand “[%var% | alt\]” strings into corresponding “val” strings from a `StrDict`, or “alt” if “var” is undefined.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrOps</a>	
<b>Arguments</b>	<code>StrBuf &amp;o</code>	the output string
	<code>StrPtr &amp;s</code>	the input string
	<code>StrDict &amp;d</code>	the var/value pairs to look up
<b>Returns</b>	void	

### Notes

Like [Expand\(\)](#), this function provides a way to quickly expand variables from a `StrDict` into a `StrBuf`, with the additional feature of providing alternate text if the value is not defined.

The exact syntax of the expression to be expanded is:

```
[ text1 %var% text2 | alt \]
```

If variable “var” has value “val” in the `StrDict d`, the expression expands to:

```
text1 val text2
```

otherwise, it expands to:

```
alt
```

See the example for details.

### Example

This small program demonstrates the [Expand2\(\)](#) method in an [OutputStat\(\)](#) implementation:

```
void MyClientUser::OutputStat( StrDict *varList )
{
    StrBuf s = StrBuf();
    s.Set( "stat: [File: %depotFile%|No file!]" );

    StrBuf o = StrBuf();
    StrOps::Expand2( o, s, *varList );

    StrOps::Dump( o );
}

int main( int argc, char **argv )
{
    ClientApi client;
    MyClientUser ui;
    Error e;

    client.SetProtocol( "tag", "" );
    client.Init( &e );

    client.SetArgv( argc - 2, argv + 2 );
    client.Run( argv[1], &ui );

    return client.Final( &e );
}
```

Executing the preceding code produces the following output:

```
% a.out files *
stat: File: //depot/src/file1.c!
stat: File: //depot/src/file2.c!

% a.out labels
stat: No file!
stat: No file!
stat: No file!
stat: No file!
stat: No file!
```

## StrOps::Indent( StrBuf &, const StrPtr & )

Make a copy of a string, with each line indented.

Virtual?	No	
Class	<a href="#">StrOps</a>	
Arguments	StrBuf &o	the output string
	StrPtr &s	the input string
Returns	void	

### Notes

This function reads the input string `s` and copies it to the output string `o`, with each line indented with a single tab.

### Example

```
StrBuf s = StrBuf();
s.Set( "abc\ndef\nghi\n" );

StrBuf o = StrBuf();
StrOps::Indent( o, s );

printf( "Before:\n%s", s.Text() );
printf( "After:\n%s", o.Text() );
```

Executing the preceding code produces the following output:

```
Before:
abc
def
ghi
After:
    abc
    def
    ghi
```



## StrOps::Lines( StrBuf &, char \*[], int )

Break a string apart at line breaks.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrOps</a>	
<b>Arguments</b>	StrBuf &o	the input string
	char *vec[]	the output array
	int maxVec	the maximum number of lines to handle
<b>Returns</b>	int	the actual number of lines handled

### Notes

This function handles all types of line breaks: “\r”, “\n”, and “\r\n”.

### Example

```
StrBuf o = StrBuf();
o.Set( "abc\ndef\nghi\n" );

printf( "Input StrBuf:\n%s\n", o.Text() );

char *vec[4];
int l = StrOps::Lines( o, vec, 4 );

for ( ; l ; l-- )
{
    printf( "Line %d: %s\n", l, vec[l-1] );
}
```

Executing the preceding code produces the following output:

```
Input StrBuf:
abc
def
ghi

Line 3: abc
Line 2: def
Line 1: ghi
```

## StrOps::Lower( StrBuf & )

Convert each character in a string (in place) to lowercase

Virtual?	No	
Class	<a href="#">StrOps</a>	
Arguments	StrBuf &o	the string to convert to lowercase
Returns	void	

### Notes

This function modifies an original string in place by converting all uppercase characters to lowercase.

### Example

```
StrBuf o = StrBuf();
o.Set( "xYzZy" );

printf( "Before: %s\n", o );
StrOps::Lower( o );
printf( "After: %s\n", o );

return 0;
```

Executing the preceding code produces the following output:

```
% a.out
Before: xYzZy
After:  xyzy
```

**StrOps::OtoX( const unsigned char \*, int, StrBuf & )**

Convert an octet stream into hex.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrOps</a>	
<b>Arguments</b>	<code>char *octet</code>	the input stream
	<code>int len</code>	length of the input in bytes
	<code>StrBuf &amp;x</code>	the output string
<b>Returns</b>	<code>void</code>	

**Notes**

This function converts the input stream into a string of hexadecimal numbers, with each byte from the input being represented as exactly two hex digits.

**Example**

```
const unsigned char stream[3] = { 'f', 'o', 'o' };
StrBuf hex;
StrOps::OtoX( stream, 3, hex );
StrOps::Dump( hex );
return 0;
```

Executing the preceding code produces the following output:

```
% a.out
666F6F
```

**StrOps::Replace( StrBuf &, const StrPtr &, const StrPtr &, const StrPtr & )**

Replace substrings in a StrPtr and store the result to a StrBuf.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrOps</a>	
<b>Arguments</b>	StrBuf &o	the output string
	StrPtr &i	the input string
	StrBuf &s	the substring to match
	StrPtr &r	the substring to replace s
<b>Returns</b>	void	

**Notes**

This function reads the input string *i* and copies it to the output string *o*, after replacing each occurrence of the string *s* with string *r*.

**Example**

```
StrBuf i = StrBuf();
i.Set( "PerForce is PerForce, of course, of course!" );

StrBuf wrong, right;
wrong.Set( "PerForce" );
right.Set( "Perforce" );

StrBuf o = StrBuf();

StrOps::Replace( o, i, wrong, right );

StrOps::Dump( o );
```

Executing the preceding code produces the following output:

```
% a.out
Perforce is Perforce, of course, of course!
```

## StrOps::Sub( StrPtr &, char, char )

Substitute instances of one character for another.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrOps</a>	
<b>Arguments</b>	<b>StrPtr &amp;string</b>	the string on which to operate
	<b>target</b>	the target character
	<b>replace</b>	the character with which to replace <b>target</b>
<b>Returns</b>	void	

### Notes

This function substitutes the **replace** character for every instance of the **target** character in the input **string**. The substitution is performed in place.

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>
#include <strops.h>

int main( int argc, char **argv )
{
    StrBuf sb;
    sb.Set( "\tPassword" );

    StrOps::Sub( sb, 'o', '0' );
    StrOps::Sub( sb, 'a', '4' );

    StrOps::Dump( sb );

    return 0;
}
```

Executing the preceding code produces the following output:

```
P4ssw0rd
```

## StrOps::Upper( StrBuf & )

Convert each character in a string (in place) to uppercase

Virtual?	No	
Class	<a href="#">StrOps</a>	
Arguments	StrBuf &o	the string to convert to uppercase
Returns	void	

### Notes

This function modifies an original string in place by converting all lowercase characters to uppercase.

### Example

```
StrBuf o = StrBuf();
o.Set( "xYzZy" );

printf( "Before: %s\n", o );
StrOps::Upper( o );
printf( "After: %s\n", o );

return 0;
```

Executing the preceding code produces the following output:

```
% a.out
Before: xYzZy
After:  XYZZY
```

**StrOps::Words( StrBuf &, const char \*[], char \*[], int )**

Break a string apart at whitespace.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrOps</a>	
<b>Arguments</b>	StrBuf &tmp	a temporary string
	const char *buf	the input string
	char *vec[]	the output array
	int maxVec	the maximum number of words to handle
<b>Returns</b>	int	the actual number of words handled

**Notes**

This function uses the `isAspace()` function to define whitespace.

**Example**

```
StrBuf o = StrBuf();
StrBuf tmp = StrBuf();
o.Set( "abc\tdef  ghi\nxyz xyzy plugh" );

printf( "Input StrBuf:\n%s\n", o.Text() );

char *vec[5];
int w = StrOps::Words( tmp, o, vec, 5 );

for ( ; w ; w-- )
{
    printf( "Word %d: %s\n", w, vec[w-1] );
}

return 0;
```

Executing the preceding code produces the following output:

```
Input StrBuf:
abc  def  ghi
xyz xyzy plugh

Word 5: xyzy
Word 4: xyz
Word 3: ghi
Word 2: def
Word 1: abc
```

**StrOps::Xto0( char \*, unsigned char \*, int )**

Convert a hex string into an octet stream.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrOps</a>	
<b>Arguments</b>	char *x	the input hex string
	char *octet	the output stream
	int octlen	the length of the output, in bytes
<b>Returns</b>	void	

**Notes**

This function converts the input hexadecimal string into the stream of bytes that it represents.

**Example**

```
char *hex = "666F6F";
unsigned char oct[4];

StrOps::Xto0( hex, oct, 3 );
oct[3] = '\0';

printf( "%s", oct );

return 0;
```

Executing the preceding code produces the following output:

```
% a.out
foo
```



## StrPtr methods

### StrPtr::Atoi()

Return the numeric value, if any, represented by this **StrPtr**'s buffer.

Virtual?	No	
Class	<a href="#">StrPtr</a>	
Arguments	None	
Returns	int	integer value of the string

### Notes

[StrPtr::Atoi\(\)](#) is equivalent to calling `atoi(StrPtr::Text\(\))`. Non-numeric strings typically return a value of zero.

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;
    StrBuf str2;

    str1.Set( "123" );
    str2.Set( "234" );

    printf( "%s + %s = %d\n",
           str1.Text(), str2.Text(), str1.Atoi() + str2.Atoi() );
}
```

Executing the preceding code produces the following output:

```
123 + 234 = 357
```

## StrPtr::CCompare( const StrPtr & )

Case insensitive comparison of two StrPtrs.

Virtual?	No	
Class	<a href="#">StrPtr</a>	
Arguments	const StrPtr &s	the StrPtr to compare this one with
Returns	int	zero if identical, nonzero if different

### Notes

[StrPtr::CCompare\(\)](#) is a wrapper for `stricmp()` or `strcasemp()`. Its return value, if nonzero, indicates which of the two strings is "greater" in the ASCII sense.

### See also

[StrPtr::XCompare\(\)](#) [StrPtr::Compare\(\)](#)

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1, str2, str3;

    str1.Set( "abc" );
    str2.Set( "Abc" );
    str3.Set( "xyz" );

    if ( str1.CCompare( str2 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str2.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str2.Text() );

    if ( str1.CCompare( str3 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str3.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str3.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
abc == Abc
abc != xyz
```

## StrPtr::Compare( const StrPtr & )

Comparison of two StrPtrs, with case sensitivity based on client platform.

Virtual?	No	
Class	<a href="#">StrPtr</a>	
Arguments	const StrPtr &s	the StrPtr to compare this one with
Returns	int	zero if identical, nonzero if different

### Notes

[StrPtr::Compare\(\)](#) is a wrapper for `zstrcmp()`. Its return value, if nonzero, indicates which of the two strings is "greater" in the ASCII sense.

### See also

[StrPtr::CCompare\(\)](#) [StrPtr::XCompare\(\)](#).

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1, str2, str3;
    str1.Set( "abc" );
    str2.Set( "Abc" );
    str3.Set( "xyz" );

    if ( str1.Compare( str2 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str2.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str2.Text() );

    if ( str1.Compare( str3 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str3.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str3.Text() );

    return 0;
}
```

Executing the preceding code produces the following output on Windows:

```
abc == Abc
abc != xyz
```

and on Unix

```
abc != Abc  
abc != xyz
```

## StrPtr::Contains( const StrPtr & )

Look for a substring and, if found, return it.

Virtual?	No	
Class	<a href="#">StrPtr</a>	
Arguments	const StrPtr &s	the substring to look for
Returns	char *	the start of the substring if found, otherwise <b>NULL</b>

### Notes

[StrPtr::Contains\(\)](#) returns a pointer to the **StrPtr**'s buffer, rather than allocating a new buffer for the substring. If it cannot find the substring, [Contains\(\)](#) returns **NULL**.

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1, str2;

    str1.Set( "the quick brown fox jumps over the lazy dog" );
    str2.Set( "brown fox" );

    printf( "%s\n", str1.Contains( str2 ) );

    return 0;
}
```

Executing the preceding code produces the following output:

```
brown fox jumps over the lazy dog
```

## StrPtr::Length()

Return the length of this StrPtr.

Virtual?	No	
Class	<a href="#">StrPtr</a>	
Arguments	None	
Returns	int	the length of this StrPtr

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "This string" );

    printf( "%s is %d bytes long\n", str1, str1.Length() );
    return 0;
}
```

Executing the preceding code produces the following output:

```
This string is 11 bytes long
```

## StrPtr::operator []( int )

Return the character at the specified index.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrPtr</a>	
<b>Arguments</b>	int x	the index to look in
<b>Returns</b>	char	the character at that index

### Notes

This operator does no bounds checking, and can therefore return data from beyond the end of the string.

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "the quick brown fox jumps over the lazy dog" );

    printf( "%c%c%c%c%c\n", str1[1], str1[2], str1[35], str1[35], str1[12] );

    return 0;
}
```

Executing the preceding code produces the following output:

```
hello
```

**StrPtr::operators ==, !=, >, <, <=, >= ( const char \* )**

Case-sensitive comparison operators between `StrPtr` and `char *`.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StrPtr</a>	
<b>Arguments</b>	<code>const char *buf</code>	the string to compare with
<b>Returns</b>	<code>int</code>	zero if the comparison is false, nonzero if true.

**Notes**

These operators are typically used in simple comparisons between `StrPtr`s, such as to see whether two `StrPtr`s contain the same string, or whether one is greater than the other, ASCII-wise. The comparison is always case-sensitive.

**Example**

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "This string" );

    printf( "%s", str1.Text());
    if ( str1 == "that string" ) printf( " == " );
    if ( str1 > "that string" ) printf( " > " );
    if ( str1 < "that string" ) printf( " < " );
    printf( "that string" );
    return 0;
}
```

Executing the preceding code produces the following output:

```
This string < that string
```

(Note that "t" > "T" in ASCII.)



## StrPtr::operators ==, !=, >, <, <=, >= ( const StrPtr & )

Case-sensitive comparison operators between StrPtr and StrPtr.

Virtual?	No	
Class	<a href="#">StrPtr</a>	
Arguments	const StrPtr & buf	the string to compare with
Returns	int	zero if the comparison is false, nonzero if true.

### Notes

These operators are typically used in simple comparisons between StrPtrs, such as to see whether two StrPtrs contain the same string, or whether one is greater than the other, ASCII-wise. The comparison is always case-sensitive.

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1, str2;

    str1.Set( "This string" );
    str2.Set( "that string" );

    printf( "%s", str1.Text());
    if ( str1 == str2 ) printf( " == " );
    if ( str1 > str2 ) printf( " > " );
    if ( str1 < str2 ) printf( " < " );
    printf( "%s\n", str2.Text() );
    return 0;
}
```

Executing the preceding code produces the following output:

```
This string < that string
```

(Note that "t" > "T" in ASCII.)

## StrPtr::Text()

Return the `char *` containing this `StrPtr`'s text.

Virtual?	No	
Class	<a href="#">StrPtr</a>	
Arguments	None	
Returns	<code>char *</code>	This <code>StrPtr</code> 's buffer

### Notes

[StrPtr::Text\(\)](#) and [StrPtr::Value\(\)](#) are exactly equivalent. Their most typical use is converting a `StrPtr` to a `char *` for functions outside of the client API to use.

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "the quick brown fox jumps over the lazy dog" );

    printf( "%s\n", str1.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
the quick brown fox jumps over the lazy dog
```

## StrPtr::Value()

Return the `char *` containing this `StrPtr`'s text.

Virtual?	No	
Class	<a href="#">StrPtr</a>	
Arguments	None	
Returns	<code>char *</code>	This <code>StrPtr</code> 's buffer

### Notes

[StrPtr::Value\(\)](#) is the deprecated form of [StrPtr::Text\(\)](#). The two functions are equivalent. Their most typical use is converting a `StrPtr` to a `char *` for functions outside of the client API to use.

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "the quick brown fox jumps over the lazy dog" );

    printf( "%s\n", str1.Value() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
the quick brown fox jumps over the lazy dog
```

## StrPtr::XCompare( const StrPtr & )

Case sensitive comparison of two StrPtrs.

Virtual?	No	
Class	<a href="#">StrPtr</a>	
Arguments	const StrPtr &s	the StrPtr to compare this one with
Returns	int	zero if identical, nonzero if different

### Notes

[StrPtr::XCompare\(\)](#) is a wrapper for `strcmp()`. Its return value, if nonzero, indicates which of the two strings is "greater" in the ASCII sense.

### See also

[StrPtr::CCompare\(\)](#) [StrPtr::Compare\(\)](#)

### Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1, str2, str3;

    str1.Set( "abc" );
    str2.Set( "Abc" );
    str3.Set( "xyz" );

    if ( str1.XCompare( str2 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str2.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str2.Text() );

    if ( str1.XCompare( str3 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str3.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str3.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
abc != Abc
abc != xyz
```

## StrRef methods

---

### StrRef::StrRef() (constructor)

Construct a `StrRef`, and leave it unset.

Virtual?	No
Class	<a href="#">StrRef</a>
Arguments	None

### Notes

If arguments are provided, the constructor calls [Set\(\)](#) with them.

## StringRef::StringRef( const StrPtr & ) (constructor)

Construct a `StringRef`, referencing an existing string.

Virtual?	No
Class	<a href="#">StringRef</a>
Arguments	<code>const StrPtr &amp;</code> a <code>StrPtr</code> to reference
Returns	<code>StringRef</code>

### Notes

If arguments are provided, the constructor calls [Set\(\)](#) with them.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "abc" );
    StringRef sr = StringRef( str1 );

    cout << "str1 = \"" << str1.Text() << "\"\n";
    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
str1 = "abc"
sr.Text() returns "abc"
```

## StringRef::StringRef( const char \* ) (constructor)

Construct a `StringRef`, referencing an existing string.

Virtual?	No	
Class	<a href="#">StringRef</a>	
Arguments	<code>char *buf</code>	a null-terminated string to reference
Returns	<code>StringRef</code>	

### Notes

If arguments are provided, the constructor calls [Set\(\)](#) with them.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "abc";
    StringRef sr = StringRef( chars );

    cout << "chars[] = \"\" << chars << "\"\n";
    cout << "sr.Text() returns \"\" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "abc"
sr.Text() returns "abc"
```

## StringRef::StringRef( const char \* , int ) (constructor)

Construct a `StringRef`, referencing an existing string.

Virtual?	No	
Class	<a href="#">StringRef</a>	
Arguments	<code>char *buf</code>	a null-terminated string to reference
	<code>int len</code>	the string length
Returns	<code>StringRef</code>	

### Notes

If arguments are provided, the constructor calls [Set\(\)](#) with them.

[StringRef::Set\(\)](#) does not copy the target string; it simply creates a pointer to it. Be sure that the `StringRef` pointing to the target string does not outlive the target string.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyzy";
    StringRef sr = StringRef( chars, 3 );
    StrBuf sb;
    sb.Set( sr );

    printf( "chars[] = \"%s\"\n", chars );
    printf( "sr.Text() returns \"%s\"\n", sr.Text() );
    printf( "sb.Text() returns \"%s\"\n", sb.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyzy"
sr.Text() returns "xyzy"
sb.Text() returns "xyz"
```



## StringRef::Null()

Return a null StrPtr.

Virtual?	No	
Class	<a href="#">StringRef</a>	
Arguments	None	
Returns	StrPtr	an empty StrPtr

### Notes

[StringRef::Null\(\)](#) is a static function.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "abc" );
    StrRef sr = StrRef( str1 );

    if ( sr == StrRef::Null() )
        cout << "str1 was null\n";
    else
        cout << "str1 was not null\n";
}
```

Executing the preceding code produces the following output:

```
str1 was not null
```

## StringRef::operator =( StrPtr & )

Set a StrPtr to reference an existing StrPtr or null-terminated string.

Virtual?	No	
Class	<a href="#">StringRef</a>	
Arguments	StrPtr &s	the StrPtr to reference
Returns	void	

### Notes

The = operator is equivalent to calling [Set\(\)](#).

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "xyz" );
    StrRef sr = str1;

    cout << "str1 = \"" << str1.Text() << "\"\n";
    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
str1 = "xyz"
sr.Text() returns "xyz"
```

## StringRef::operator=( char \* )

Set a StrPtr to reference an existing StrPtr or null-terminated string.

Virtual?	No	
Class	<a href="#">StringRef</a>	
Arguments	char *buf	the null-terminated string to reference.
Returns	void	

### Notes

The = operator is equivalent to calling [Set\(\)](#).

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyz";
    StrRef sr;

    sr = chars;

    cout << "chars[] = \"\" << chars << "\"\n";
    cout << "sr.Text() returns \"\" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyz"
sr.Text() returns "xyz"
```

## StringRef::operator +=( int )

Increase a `StringRef`'s pointer and decrease its length.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StringRef</a>	
<b>Arguments</b>	<code>int len</code>	the amount by which to move the pointer
<b>Returns</b>	<code>void</code>	

### Notes

This method has the effect of removing `len` characters from the beginning of the `StringRef`. It does not, however, free the memory allocated to those characters.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyzy";
    StringRef sr = StringRef( chars );

    sr += 3;

    cout << "chars[] = \"\" << chars << "\"\n";
    cout << "sr.Text() returns \"\" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyzy"
sr.Text() returns "zy"
```

## StringRef::Set( char \* )

Set a `StringRef` to reference an existing null-terminated string.

Virtual?	No	
Class	<a href="#">StringRef</a>	
Arguments	<code>char *buf</code>	the null-terminated string to reference
Returns	<code>void</code>	

### Notes

[StringRef::Set\(\)](#) does not copy the target string; it simply establishes a pointer to it. Be sure that the `StringRef` pointing to the target string does not outlive the target string.

### Example

```
#include <iostream>

#include <string.h>
#include <stringbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyz";
    StringRef sr;

    sr.Set( chars );

    cout << "chars[] = \"\" << chars << "\"\n";
    cout << "sr.Text() returns \"\" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyz"
sr.Text() returns "xyz"
```

## StringRef::Set( char \*, int )

Set a `StringRef` to reference an existing null-terminated string.

<b>Virtual?</b>	No	
<b>Class</b>	<a href="#">StringRef</a>	
<b>Arguments</b>	<code>char *buf</code>	the null-terminated string to reference
	<code>int len</code>	the length of the string
<b>Returns</b>	<code>void</code>	

### Notes

[StringRef::Set\(\)](#) does not copy the target string; it simply establishes a pointer to it. Be sure that the `StringRef` pointing to the target string does not outlive the target string.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyzy";
    StrBuf sb;
    StrRef sr;
    sb.Set( chars );
    sr.Set( chars, 3 );

    printf( "chars[] = \"%s\\n\", chars );
    printf( "sr.Text() returns \"%s\\n\", sr.Text() );
    printf( "sb.Text() returns \"%s\\n\", sb.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyzy"
sr.Text() returns "xyzy"
sb.Text() returns "xyz"
```

## StringRef::Set( const StrPtr \* )

Set a `StringRef` to reference an existing `StrPtr`.

Virtual?	No	
Class	<a href="#">StringRef</a>	
Arguments	<code>const StrPtr *s</code>	the value to set
Returns	<code>void</code>	

### Notes

[StringRef::Set\(\)](#) does not copy the target string; it simply establishes a pointer to it. Be sure that the `StringRef` pointing to the target string does not outlive the target string.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StringRef sr;
    sr.Set( "xyz" );

    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sr.Text() returns "xyz"
```

## StringRef::Set( const StrPtr & )

Set a StrRef to reference an existing StrPtr.

Virtual?	No
Class	<a href="#">StringRef</a>
Arguments	const StrPtr &s    the StrPtr to reference
Returns	void

### Notes

[StringRef::Set\(\)](#) does not copy the target string; it simply establishes a pointer to it. Be sure that the StrRef pointing to the target string does not outlive the target string.

### Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;
    StrRef sr;

    str1.Set ( "xyz" );
    sr.Set( str1 );

    cout << "str1 = \"\" << str1.Text() << "\"\n";
    cout << "sr.Text() returns \"\" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
str1 = "xyz"
sr.Text() returns "xyz"
```



Perforce software includes software developed by the University of California, Berkeley and its contributors. This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>).

Perforce software includes software from the Apache ZooKeeper project, developed by the Apache Software Foundation and its contributors. (<http://zookeeper.apache.org/>)

Perforce software includes software developed by the OpenLDAP Foundation (<http://www.openldap.org/>).

Perforce software includes software developed Computing Services at Carnegie Mellon University: Cyrus SASL (<http://www.cmu.edu/computing/>).

